



Orbacus™

Using Orbacus

Version 4.3, January 2007

IONA Technologies PLC and/or its subsidiaries may have patents, patent applications, trademarks, copyrights, or other intellectual property rights covering subject matter in this publication. Except as expressly provided in any written license agreement from IONA Technologies PLC, the furnishing of this publication does not give you any license to these patents, trademarks, copyrights, or other intellectual property. Any rights not expressly granted herein are reserved.

IONA, IONA Technologies, the IONA logos, Orbix, Artix, Making Software Work Together, Adaptive Runtime Technology, Orbacus, IONA University, and IONA XMLBus are trademarks or registered trademarks of IONA Technologies PLC and/or its subsidiaries.

Java and J2EE are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and other countries. CORBA is a trademark or registered trademark of the Object Management Group, Inc. in the United States and other countries. All other trademarks that appear herein are the property of their respective owners.

IONA Technologies PLC makes no warranty of any kind to this material including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. IONA Technologies PLC shall not be liable for errors contained herein, or for incidental or consequential damages in connection with the furnishing, performance or use of this material.

COPYRIGHT NOTICE

No part of this publication may be reproduced, stored in a retrieval system or transmitted, in any form or by any means, photocopying, recording or otherwise, without prior written consent of IONA Technologies PLC. No third party intellectual property right liability is assumed with respect to the use of the information contained herein. IONA Technologies PLC assumes no responsibility for errors or omissions contained in this book. This publication and features described herein are subject to change without notice.

Copyright © 2001-2007 IONA Technologies PLC. All rights reserved.

All products or services mentioned in this manual are covered by the trademarks, service marks, or product names as designated by the companies who market those products.

Updated: November 4, 2009

Contents

List of Tables	13
List of Figures	15
Preface	17
Chapter 1 Introduction to Orbacus	21
Overview	22
Chapter 2 Getting Started	25
The Hello World Example Application	26
Defining the Example in IDL	27
Implementing the Example in C++	28
Implementing the Server	29
Writing the Server Program	31
Implementing the Client	35
Compiling and Linking	37
Running the Application	38
Implementing the Example in Java	39
Implementing the Server	40
Implementing the Client	45
Compiling	47
Running the Application	48
Summary	49
Where To Go From Here	50
Chapter 3 Generating Code with Orbacus	51
Orbacus Translators	52
Translating IDL to C++	53
Translating IDL to Java	57
Translating IDL to HTML	59
Translating IDL to RTF	60

Generating C++ from an Interface Repository	62
The IDL-to-C++ Translator and the Interface Repository	63
Include Statements	64
Documenting IDL Files	65
Using javadoc	68
Chapter 4 ORB and Object Adapter Initialization	73
Initializing the C++ ORB	74
Initializing the Java ORB	75
Object Adapter Initialization	76
Configuring the ORB and Object Adapter	77
ORB Properties	78
OA Properties	85
Command-line Options	88
Using a Configuration File	90
Using the Windows Registry	91
Defining Properties	92
Precedence of Properties	94
Advanced Property Usage	95
Using POA Managers	97
The Root POA Manager	98
Anonymous POA Managers	99
The POA Manager Factory	100
Creating a POA Manager	101
POA Manager Policies	103
Endpoints	104
Command-line Options and Endpoints	105
Dispatching Requests	106
Callbacks	107
ORB Destruction	108
Server Event Loop	109
Chapter 5 CORBA Objects	111
Overview	112
Implementing Servants	114
Implementing Servants using Inheritance	115
Implementing Servants using Delegation	118
Creating Servants	123

Creating Servants using C++	124
Creating Servants using Java	126
Activating Servants	128
Implicit Activation of Servants using C++	129
Implicit Activation of Servants using Java	130
Explicit Activation of Servants using C++	131
Explicit Activation of Servants using Java	132
Deactivating Servants	133
Factory Objects	135
Factory Objects using C++	137
Factory Objects using Java	140
Caveats	141
Obtaining the POA for a Servant	142
Getting the POA for a Currently Executing Request	144
Chapter 6 Locating Objects	147
Obtaining Object References	148
Lifetime of Object References	152
Hostname	153
Port Number	154
Object Key	155
Stringified Object References	156
Using a File	157
Using a URL	159
Object Reference URLs	160
corbaloc: URLs	161
corbaname: URLs	163
file: URLs	164
relfile: URLs	165
The BootManager	166
BootManager Interface	167
How the BootManager Works	168
Using the BootManager	169
Initial Services	170
Resolving an Initial Service	171
Configuring the Initial Services	173
The Initial Service Locator	175
The IORDump utility	176

Chapter 7 The Implementation Repository	179
Background	181
Information Managed by the IMR	182
IMR Security	185
Usage	186
Windows Native Service	188
Configuration Properties	190
Connecting to the Service	191
Utilities	192
Getting Started with the Implementation Repository	195
Programming Example	198
Chapter 8 The Implementation Repository Console	203
Usage	204
The Menus	205
Chapter 9 Orbacus Names	209
Usage	211
Windows Native Service	213
Configuration Properties	215
Persistence	216
Connecting to the Service	217
Using the Naming Service with the IMR	218
Bindings	219
Name Resolution	221
Programming Example	222
Initialization	223
Binding	225
Exceptions	228
The Event Loop	230
Releasing Resources	231
Chapter 10 Orbacus Names Console	233
Usage	234
Naming Service Lookup	235
The Menus	236
The Edit Menu	238
The View Menu	240

The Tools Menu	242
The Toolbar	244
The Popup Menu	245
Chapter 11 Orbacus Properties	247
Usage	248
Connecting to the Service	250
Using the Property Service with the IMR	251
Creating Properties	252
Querying for Properties	253
Deleting Properties	255
Programming Example	256
Chapter 12 Orbacus Events	259
Usage	260
Windows Native Service	261
Configuration Properties	263
Connecting to the Service	265
Using the Event Service with the IMR	266
Event Service Concepts	267
The Event Channel	268
Event Suppliers and Consumers	269
Event Channel Policies	271
Event Channel Factories	272
Programming Example	275
Chapter 13 The Interface Repository	279
Usage	280
Windows Native Service	281
Configuration Properties	283
Connecting to the Interface Repository	284
Configuration Issues	285
Interface Repository Utilities	286
Programming Example	287
Chapter 14 Orbacus Balancer	289
Basic Concepts	290
Load Balancing Strategies	291

Service Security	294
Usage	295
Windows Native Service	296
Configuration Properties	298
Built-in Load Balancing Strategies	300
Connecting to the Service	303
Load Balanced IMR-enabled Servers	304
Utilities	305
Service Administration	306
Making References	307
Utility Objects	308
Utility Object Configuration Properties	309
Programming Example	310
Non-adaptive Load Balancing	311
Adaptive Load Balancing	315
Running the Load Balanced Servers	320
Chapter 15 Orbacus Watson	323
Tracing Levels	324
Installing Watson in C++	325
Installing Watson in Java	326
Configuration Properties	327
Sample Configuration File	328
Chapter 16 Using Policies	329
Overview	330
Supported Policies	331
Programming Examples	334
Connection Reuse Policy	335
Retry Policy	338
Timeout Policy	340
Interceptor Call Policy	341
CommunicationsConcurrencyPolicy	343
EndpointConfigurationPolicy	345
GIOPVersionPolicy	347
Bidirectional Policy	349

Chapter 17 Asynchronous Method Invocation	353
Introduction	354
AMI Router	355
Router Usage	356
Router Administration Properties	357
AMI Reply Handler Implementation	359
AMI Poller Implementation	363
Configuring Clients and Servers	365
Chapter 18 Concurrency Models	369
Concurrency Models	370
Single-Threaded Concurrency Model	372
Multi-Threaded Concurrency Models	375
Threaded Clients and Servers	376
Thread-per-Client Server	378
Thread-per-Request Server	379
Thread Pool Server	380
Leader_Follower	381
The Reactor	382
The X11 Reactor	383
The Windows Reactor	385
Chapter 19 The Open Communications Interface	387
Interface Summary	388
Class Diagram	390
OCI Reference	391
A Converter Class for Java	392
Getting Hostnames and Port Numbers	393
Determining a Client's IP Address	395
Determining a Server's IP Address	397
The IIOP OCI Plug-in	399
Endpoint Configuration	400
Command-line Options	402
Static Linking	403
The UDP OCI Plug-in	404
Client Installation	405
Server Installation	406
Endpoint Configuration	407

Static Linking	410
URL Support	411
Narrowing UDP Object References	412
The Bi-directional OCI Plug-in	413
How Does it Work?	415
Peers	416
Client Installation	417
Server Installation	418
Endpoint Configuration	419
Command-line Options	420
Configuration Properties	421
Static Linking	422
URL Support	423
Chapter 20 Exceptions and Error Messages	425
CORBA System Exceptions	426
INITIALIZE Minor Exception Code	429
UNKNOWN Minor Exception Code	430
BAD_PARAM Minor Exception Code	431
NO_MEMORY Minor Exception Code	433
IMP_LIMIT Minor Exception Code	434
COMM_FAILURE Minor Exception Code	435
MARSHAL Minor Exception Code	436
NO_IMPLEMENT Minor Exception Code	438
NO_RESOURCES Minor Exception Code	439
BAD_INV_ORDER Minor Exception Code	440
TRANSIENT Minor Exception Code	441
INTF_REPOS Minor Exception Code	442
OBJECT_NOT_EXIST Minor Exception Code	443
INV_POLICY Minor Exception Code	444
Non-Compliant Application Asserts	445
Appendix A Boot Manager Reference	449
Interface OB::BootManager	450
Interface OB::BootLocator	452
Appendix B Orbacus Policy Reference	453
Module OB	454

Interface OB::ConnectTimeoutPolicy	456
Interface OB::ConnectionReusePolicy	457
Interface OB::InterceptorPolicy	458
Interface OB::LocateRequestPolicy	459
Interface OB::LocationTransparencyPolicy	460
Interface OB::ProtocolPolicy	461
Interface OB::RequestTimeoutPolicy	462
Interface OB::RetryPolicy	463
Interface OB::TimeoutPolicy	464
Module OBPortableServer	465
Interface OBPortableServer::InterceptorCallPolicy	466
BiDirPolicy	467
Appendix C Reactor Reference	469
Module OB	470
Interface OB::Reactor	471
Appendix D Logger Reference	473
Interface OB::Logger	474
Interface OB::WLogger	475
Appendix E Open Communications Interface Reference	477
Module OCI	478
Interface OCI::Buffer	482
Interface OCI::Plugin	484
Interface OCI::Transport	485
Interface OCI::TransportInfo	490
Interface OCI::CloseCB	492
Interface OCI::Connector	493
Interface OCI::ConnectorInfo	495
Interface OCI::ConnectCB	497
Interface OCI::ConFactory	498
Interface OCI::ConFactoryInfo	500
Interface OCI::ConFactoryRegistry	501
Interface OCI::Acceptor	502
Interface OCI::AcceptorInfo	505
Interface OCI::AcceptCB	507
Interface OCI::AccFactory	508

Interface OCI::AccFactoryInfo	510
Interface OCI::AccFactoryRegistry	511
Interface OCI::Current	512
Module OCI::IIOP	513
Interface OCI::IIOP::TransportInfo	514
Interface OCI::IIOP::ConnectorInfo	515
Interface OCI::IIOP::ConFactoryInfo	516
Interface OCI::IIOP::AcceptorInfo	517
Interface OCI::IIOP::AccFactoryInfo	518
Appendix F Orbacus Balancer Reference	519
Module LoadBalancing	520
Interface LoadBalancing::LoadAlert	525
Interface LoadBalancing::Strategy	526
Interface LoadBalancing::StrategyProxy	527
Interface LoadBalancing::Group	528
Interface LoadBalancing::GroupFactory	530
Module LoadBalancing::Util	531
Interface LoadBalancing::Util::LoadAlert	532
Interface LoadBalancing::Util::LoadCalculator	533
Interface LoadBalancing::Util::LoadUpdater	534
Orbacus Bibliography	535
Index	537

List of Tables

Table 1: POA Managers' Communications Concurrency Model	86
Table 2: Object Keys and Interface Types	265
Table 3: Object Keys and Interface Types for Event Channel Factories	265
Table 4: Orbacus policies	331
Table 5: Default Concurrency Models	371

LIST OF TABLES

List of Figures

Figure 1: Documentation generated with the IDL-to-HTML translator	66
Figure 2: Servants, Proxies and the Object Adapter	112
Figure 3: Class Hierarchy for Delegation Implementation in C++	119
Figure 4: Class Hierarchy for Inheritance and Delegation Implementation in Java	121
Figure 5: Entering an IOR	237
Figure 6: The Ping Window	242
Figure 7: A closer look at the toolbar	244
Figure 8: A popup menu offers important operations	245
Figure 9: Reactive Server	372
Figure 10: Reactive Client/Server	373
Figure 11: Threaded Server	376
Figure 12: Thread-per-Client Server	378
Figure 13: Thread-per-Request Server	379
Figure 14: Thread Pool Server	380
Figure 15: OCI Class Diagram	390
Figure 16: Connection Requirements	415

LIST OF FIGURES

Preface

The Orbacus Library

The Orbacus documentation library consists of the following books:

- [Using Orbacus](#) (this book)
- [Using FreeSSL for Orbacus](#)
- [JThreads/C++](#)
- [Orbacus Notify](#)
- [.NET Connector Programmer's Guide](#)

Using Orbacus

This manual describes how Orbacus implements the CORBA standard, and describes how to develop and maintain code that uses the Orbacus ORB. This is the primary developer's guide and reference for Orbacus.

Using FreeSSL for Orbacus

This manual describes the FreeSSL plug-in, which enables secure communications using the Orbacus ORB in both Java and C++.

JThreads/C++

This manual describes JThreads/C++, which is a high-level thread abstraction library that gives C++ programmers the look and feel of Java threads.

Orbacus Notify

This manual describes Orbacus Notify, an implementation of the Object Management Group's Notification Service specification.

.NET Connector Programmer's Guide

This manual describes the Orbacus .NET Connector, which enables transparent communication between clients running in a Microsoft .NET environment and servers running in a CORBA environment.

Audience

Manuals in the Orbacus library are written for intermediate to advanced level programmers who are:

- Experienced with Java or C++ programming
- Familiar with the CORBA standard and its specifications

These manuals do not teach the CORBA specification or CORBA programming in general, which are prerequisite skills. These manuals concentrate on how Orbacus implements the CORBA standard.

Getting the Latest Version

The latest updates to the Orbacus documentation can be found at <http://www.iona.com/support/docs>.

Compare the version dates on the web page for your product version with the date printed on the copyright page of the PDF edition of the book you are reading.

Searching the Orbacus Library

You can search the online documentation by using the **Search** box at the top right of the documentation home page:

<http://www.iona.com/support/docs>

To search a particular library version, browse to the required index page, and use the **Search** box at the top right.

You can also search within a particular book. To search within a HTML version of a book, use the **Search** box at the top left of the page. To search within a PDF version of a book, in Adobe Acrobat, select **Edit | Find**, and enter your search text.

Additional Resources

The [IONA Knowledge Base](http://www.iona.com/support/knowledge_base/index.xml) (http://www.iona.com/support/knowledge_base/index.xml) contains helpful articles written by IONA experts about Orbacus and other products.

The [IONA Update Center](http://www.iona.com/support/updates/index.xml) (<http://www.iona.com/support/updates/index.xml>) contains the latest releases and patches for IONA products.

If you need help with this or any other IONA product, go to [IONA Online Support](http://www.iona.com/support/index.xml) (<http://www.iona.com/support/index.xml>).

Comments, corrections, and suggestions on IONA documentation can be sent to docs-support@iona.com.

Document Conventions

Typographical conventions

This book uses the following typographical conventions:

Fixed width Fixed width (Courier font) in normal text represents portions of code and literal names of items such as classes, functions, variables, and data structures. For example, text might refer to the `IT_Bus::AnyType` class.

Constant width paragraphs represent code examples or information a system displays on the screen. For example:

```
#include <stdio.h>
```

Fixed width italic Fixed width italic words or characters in code and commands represent variable values you must supply, such as arguments to commands or path names for your particular system. For example:

```
% cd /users/YourUserName
```

Italic Italic words in normal text represent *emphasis* and introduce *new terms*.

Bold Bold words in normal text represent graphical user interface components such as menu commands and dialog boxes. For example: the **User Preferences** dialog.

Keying Conventions

This book uses the following keying conventions:

No prompt	When a command's format is the same for multiple platforms, the command prompt is not shown.
%	A percent sign represents the UNIX command shell prompt for a command that does not require root privileges.
#	A number sign represents the UNIX command shell prompt for a command that requires root privileges.
>	The notation > represents the MS-DOS or Windows command prompt.
...	Horizontal or vertical ellipses in format and syntax descriptions indicate that material has been eliminated to simplify a discussion.
.	
.	
.	
[]	Brackets enclose optional items in format and syntax descriptions.
{ }	Braces enclose a list from which you must choose an item in format and syntax descriptions.
	In format and syntax descriptions, a vertical bar separates items in a list of choices enclosed in { } (braces). In graphical user interface descriptions, a vertical bar separates menu commands (for example, select File Open).

Introduction to Orbacus

This chapter gives a short overview of Orbacus

In this chapter

This chapter contains the following section:

Overview	page 22
--------------------------	-------------------------

Overview

What is Orbacus?

Orbacus is an Object Request Broker (ORB) that is compliant with the Common Object Request Broker Architecture (CORBA) specification as defined in “The Common Object Request Broker: Architecture and Specification” [4], “C++ Language Mapping” [5], “IDL/Java Language Mapping” [6], and “Portable Interceptors” [7].

The following sections highlight some of the features of Orbacus.

Ease of Use

- Configuration and bootstrapping is simple:
 - ◆ Daemon-less servers
 - ◆ Servers started automatically by the Implementation Repository
 - ◆ URL-style object references
 - Watson diagnostics and analysis: method tracing within the ORB
 - Extensible Logging facility: output to multiple devices
 - Documentation Tools: Translators (see [“Orbacus Translators” on page 52](#))
 - ◆ IDL to Hypertext Markup Language (HTML)
 - ◆ IDL to Rich Text Format (RTF)
 - JThreads/C++: Java-like threading for C++. (See the separate manual *JThreads/C++* in the Orbacus documentation library.)
-

Qualities of Service

- Load Balancing: balance client requests across a set of replicated objects and stateless servers.
- Fault Tolerance: transparent failover by implementing multiple profile Interoperable Object References.
- Active Connection Management: reclaim idle connections automatically, conserving threads, sockets, memory and other important system resources.
- Security: FreeSSL plug-in provides secure authentication and encryption facilities. (See the separate manual *Using FreeSSL for Orbacus.*)

- Concurrency: Single and Multithreaded models to exploit power of multiprocessor hardware.
- Dynamic Loading Of Modules: transparently install extensions and services such as transactions, interceptors, and protocol plug-ins.
- Flexibility through pluggable transport protocols. (See [“The Open Communications Interface”](#) on page 387.)

CORBA features

- CORBA 2.5 support.
- CORBA Services:
 - ◆ Naming, Events and Property services are part of the Orbacus product.
 - ◆ Orbacus interoperates with the Orbix Notification, Orbix Trader and Orbix Telecom Logging services.
- Portable Interceptors: provide a "hook" for adding code that is called upon for each operation invocation.
- Portable Object Adapter: provides high scalability for servers that contain very large numbers of objects.
- Objects by Value: reduce network traffic by turning a remote interaction into a local invocation.
- Dynamic Invocation and Dynamic Skeleton Interface: send and receive requests without compile-time knowledge of interface types and operation signatures.
- Implementation Repository: start servers on demand and migrate servers to different hosts without adversely affecting clients.
- Interface Repository: build IDL-to-anything translators easily
- Support for Local Interfaces: standard way to implement locality-constrained objects

Platform support

For platform availability, please refer to the Orbacus home page at http://www.orbacus.com/support/new_site/platforms.jsp.

About this Document

With the exception of the [Getting Started](#) chapter, this manual is not a replacement for a good CORBA book. This manual also does not contain the exact specifications of the CORBA standard, which are freely available online. A good grasp of the CORBA specifications in [\[4\]](#), [\[5\]](#), and [\[6\]](#) is

absolutely necessary to effectively use this manual. In particular, the chapters in [4], covering CORBA IDL and the IDL-to-C++ mapping, should be studied thoroughly.

For C++ users, we also highly recommend [3]. This book contains by far the best treatment of CORBA programming with C++ to date.

What this manual does contain, however, is information on *how* Orbacus implements the CORBA standard. A shortcoming of the current CORBA specification is that it leaves a high degree of freedom to the CORBA implementation. For example, the precise semantics of a oneway call are not specified by the standard.

To make it easier to get started with Orbacus, this book contains a [Getting Started](#) chapter, explaining some Orbacus basics with a very simple example.

Getting Started

This chapter introduces you to Orbacus using a well-known application: the Hello World! application is presented here in a special client-server version.

In this chapter

This chapter contains the following sections:

The Hello World Example Application	page 26
Defining the Example in IDL	page 27
Implementing the Example in C++	page 28
Implementing the Example in Java	page 39
Summary	page 49
Where To Go From Here	page 50

The Hello World Example Application

C++ and Java applications

Many books on programming start with this tiny demo program. In introductory C++ books you'll probably find the following piece of code in the first chapter:

```
// C++
#include <iostream.h>

int main(int, char*[])
{
    cout << "Hello World!" << endl;
    return 0;
}
```

Or, in introductory Java books:

```
// Java
public class Greeter
{
    public static void main(String args[])
    {
        System.out.println("Hello World!");
    }
}
```

These applications simply print Hello World! to standard output and that is exactly what this chapter is about: Printing Hello World! with a CORBA-based client-server application. In other words, we will develop a client program that invokes a `say_hello` operation on an object in a server program. The server responds by printing “Hello World!” on its standard output.

Defining the Example in IDL

CORBA-based program

How do we write a CORBA-based Hello World! program? The first step is to create a file containing our IDL definitions. Since our example application isn't a complicated one, the IDL code needed for this example is simple.

Save the IDL code shown below to a file called `Hello.idl`.

```
1 // IDL
2 interface Hello
3 {
4     void say_hello();
5 }
```

Line 2 An interface with the name `Hello` is defined. An IDL interface is conceptually equivalent to a pure abstract class in C++, or to an interface in Java.

Lines 4 The only operation defined is `say_hello`, which neither takes any parameters nor returns any result.

Implementing the Example in C++

Generating C++ from IDL

The next step is to translate the IDL code to C++ using the IDL-to-C++ translator.

Translate the code in `Hello.idl` to C++ using the following command:

```
idl Hello.idl
```

This command will create the files:

- `Hello.h`
- `Hello.cpp`
- `Hello_skel.h`
- `Hello_skel.cpp`

Now we will implement the server and client.

In this section

This section discusses the following topics:

Implementing the Server	page 29
Writing the Server Program	page 31
Implementing the Client	page 35
Compiling and Linking	page 37
Running the Application	page 38

Implementing the Server

Overview

To implement the server, we need to define an implementation class for the `Hello` interface. To do this, we create a class `Hello_impl` that is derived from the skeleton class `POA_Hello`, defined in the file `Hello_skel.h`.

Hello_impl definition

Create a file `Hello_impl.h` and enter the class definition of `Hello_impl` shown below:

```
1 // C++
2 #include <Hello_skel.h>
3
4 class Hello_impl : public POA_Hello, public
5     PortableServer::RefCountServantBase
6 {
7 public:
8
9     virtual void say_hello()
10         throw (CORBA::SystemException);
11 };
```

Line 2 Since our implementation class derives from the skeleton class `POA_Hello`, we must include the file `Hello_skel.h`.

Line 4 Here we define `Hello_impl` as a class derived from `POA_Hello` and `RefCountServantBase`. `RefCountServantBase` is part of the `PortableServer` namespace and provides reference counting.

Line 9 Our implementation class must implement all operations from the IDL interface. In this case, this is just the operation `say_hello`.

Hello_impl implementation

Create a file `Hello_impl.cpp` and enter the class implementation of `Hello_impl` shown below:

```
1 // C++
2 #include <iostream.h>
3 #include <OB/CORBA.h>
4 #include <Hello_impl.h>
5
6 void Hello_impl::say_hello() throw(CORBA::SystemException)
7 {
8     cout << "Hello World!" << endl;
9 }
```

Line 3 We must include `OB/CORBA.h`, which contains definitions for the standard CORBA classes, as well as for other useful things.

Line 4 We must also include the `Hello_impl` class definition, contained in the header file `Hello_impl.h`.

Lines 6-9 The `say_hello` function simply prints “Hello World!” on standard output.

Writing the Server Program

Overview

Now we will write the server program. To simplify exception handling and ORB destruction, we will split the server into two functions: `main()` and `run()`, where `main()` only creates the ORB, and calls `run()`

`main()` function

Create a file with the name `Server.cpp` and enter the code for the `main()` function shown below:

```
1 // C++
2 #include <OB/CORBA.h>
3 #include <Hello_impl.h>
4
5 #include <fstream.h>
6
7 int run(CORBA::ORB_ptr);
8
9 int main(int argc, char* argv[])
10 {
11     int status = EXIT_SUCCESS;
12     CORBA::ORB_var orb;
13
14     try
15     {
16         orb = CORBA::ORB_init(argc, argv);
17         status = run(orb);
18     }
19     catch(const CORBA::Exception&)
20     {
21         status = EXIT_FAILURE;
22     }
23 }
```

```

24     if(!CORBA::is_nil(orb))
25     {
26         try
27         {
28             orb -> destroy();
29         }
30         catch(const CORBA::Exception&)
31         {
32             status = EXIT_FAILURE;
33         }
34     }
35
36     return status;
37 }

```

Lines 2-5 Several header files are included. Of these, `OB/CORBA.h` provides the standard CORBA definitions, and `Hello_impl.h` contains the definition of the `Hello_impl` class.

Line 7 A forward declaration for the `run()` function.

Line 16 The first thing a CORBA program must do is initialize the ORB. This operation expects the parameters with which the program was started. These parameters may or may not be used by the ORB, depending on the CORBA implementation. Orbacus recognizes certain options that will be explained later.

Line 17 The `run()` helper function is called.

Lines 19-22 This code catches and prints all CORBA exceptions raised by `ORB_init()` or `run()`.

Lines 24-34 If the ORB was successfully created, it is destroyed. This releases the resources used by the ORB. If `destroy()` raises a CORBA exception, this exception is caught and printed.

Line 36 The exit status is returned. If there was no error, `EXIT_SUCCESS` is returned, or `EXIT_FAILURE` otherwise.

run() function

Add the code for the `run()` function to `Server.cpp`:

```
1 // C++
2 int run(CORBA::ORB_ptr orb)
3 {
4     CORBA::Object_var poaObj =
5         orb -> resolve_initial_references("RootPOA");
6     PortableServer::POA_var rootPoa =
7         PortableServer::POA::_narrow(poaObj);
8
9     PortableServer::POAManager_var manager =
10        rootPoa -> the_POAManager();
11
12     Hello_impl* helloImpl = new Hello_impl();
13     PortableServer::ServantBase_var servant = helloImpl;
14     Hello_var hello = helloImpl -> _this();
15
16     CORBA::String_var s = orb -> object_to_string(hello);
17     const char* refFile = "Hello.ref";
18     ofstream out(refFile);
19     out << s << endl;
20     out.close();
21
22     manager -> activate();
23     orb -> run();
24
25     return EXIT_SUCCESS;
25 }
```

Lines 4-7 Using the ORB reference, `resolve_initial_references()` is invoked to obtain a reference to the Root POA.

Lines 9-10 The Root POA is used to obtain a reference to its POA Manager.

Lines 12-14 A servant of type `Hello_impl` is created and assigned to a `ServantBase_var` variable. The servant is then used to incarnate a CORBA object, using the `_this()` operation. `ServantBase_var` and `Hello_var`, like all `_var` types, are smart pointers. That is, `servant` and `hello` will release their assigned object automatically when they go out of scope.

Lines 16-20 The client must be able to access the implementation object. This can be done by saving a stringified object reference to a file, which can then be read by the client and converted back to the actual object reference.¹ The operation `object_to_string()` converts a CORBA object reference into its string representation.

Lines 22-23 The server must activate the POA Manager to allow the Root POA to start processing requests, and then inform the ORB that it is ready to accept requests.

1. If your application contains more than one object, you do not need to save object references for all objects. Usually you save the reference of one object which provides operations that can subsequently return references to other objects.

Implementing the Client

Overview

In several respects, the client program is similar to the server program. The code to initialize and destroy the ORB is the same.

Client code

Save the following code in a file `Client.cpp`:

```
1 // C++
2 #include <OB/CORBA.h>
3 #include <Hello.h>
4
5 #include <fstream.h>
6
7 int run(CORBA::ORB_ptr);
8
9 int main(int argc, char* argv[])
10 {
11     ... // Same as for the server
12 }
13
14 int run(CORBA::ORB_ptr orb)
15 {
16     const char* refFile = "Hello.ref";
17     ifstream in(refFile);
18     char s[2048];
19     in >> s;
20     CORBA::Object_var obj = orb -> string_to_object(s);
21
22     Hello_var hello = Hello::_narrow(obj);
23
24     hello -> say_hello();
25
26     return 0;
27 }
```

Line 3 In contrast to the server, the client does not need to include `Hello_impl.h`. Only the generated file `Hello.h` is needed.

Lines 7-12 This code is the same as for the server.

Lines 16-20 The stringified object reference written by the server is read and converted to a `CORBA::Object` object reference. It's not necessary to obtain a reference to the Root POA or its POA Manager, because they are only needed by server applications.

Line 22 The `_narrow` operation generates a `Hello` object reference from the `CORBA::Object` object reference. Although `_narrow` for CORBA objects works similar to `dynamic_cast<>` for plain C++ objects, `dynamic_cast<>` must not be used for CORBA object references. That's because in contrast to `dynamic_cast<>`, `_narrow` might have to query the server for type information.

Line 24 The `say_hello` operation on the `hello` object reference is invoked, causing the server to print "Hello World!".

Compiling and Linking

Overview

Compiling `Hello.cpp` results in an object file with the following name:

- **UNIX:** `Hello.o`
- **Windows:** `Hello.obj`

You must link both the client and the server with the file for your platform.

The compiled `Hello_skel.cpp` and `Hello_impl.cpp` are only needed by the server.

Dependencies

Compiling and linking is to a large degree compiler- and platform-dependent. Many compilers require unique options to generate correct code.

To build Orbacus programs, you must at least link with the Orbacus library for your platform:

- **UNIX:** `libOB.a`
- **Windows:** `ob.lib`

Additional libraries are required on some systems, such as `libsocket.a` and `libns1.a` for Solaris or `wsock32.lib` for Windows.

For more details

The Orbacus distribution includes various `README` files for different platforms which give hints on the options needed for compiling and the libraries necessary for linking. Please consult these `README` files for details.

Running the Application

Overview

Our Hello World! application consists of two parts:

- The client program
- The server program

Start the server first, since it must create the file `Hello.ref` that the client needs in order to connect to the server. As soon as the server is running, you can start the client. If all goes well, the Hello World! message will appear on the screen.

Implementing the Example in Java

Generating Java from IDL

In order to implement this application in Java, the interface specified in IDL is translated to Java classes similar to the way the C++ code was created.

Translate the code in `Hello.idl` to Java using the following command:

```
jidl --package hello Hello.idl
```

This command generates several Java source files on which the actual implementation will be based:

- `Hello.java`
- `HelloHelper.java`
- `HelloHolder.java`
- `HelloOperations.java`
- `HelloPOA.java`
- `_HelloStub.java`

All these files are generated into a directory with the name `hello`.

In this section

This section discusses the following topics:

Implementing the Server	page 40
Implementing the Client	page 45
Compiling	page 47
Running the Application	page 48

Implementing the Server

Implementation class

Create a file `Hello_impl.java` in the directory `hello` and enter the following code for the server's `Hello` implementation class:

```
1 // Java
2 package hello;
3
4 public class Hello_impl extends HelloPOA
5 {
6     public void say_hello()
7     {
8         System.out.println("Hello World!");
9     }
10 }
```

Line 4 The implementation class `Hello_impl` must inherit from the generated class `HelloPOA`.

Lines 6-8 As with the C++ implementation, the `say_hello` method simply prints “Hello World!” on standard output.

Server class main() method

Create a file `Server.java` in the directory `hello` and enter the following `Server` class code which holds the server's `main()` and `run()` methods:

```
1 // Java
2 package hello;
3
4 public class Server
5 {
6     public static void main(String args[])
7     {
8         java.util.Properties props = System.getProperties();
9         props.put("org.omg.CORBA.ORBClass",
10                "com.ooc.OBServer.ORB");
11         props.put("org.omg.CORBA.ORBSingletonClass",
12                "com.ooc.CORBA.ORBSingleton");
13
14         int status = 0;
15         org.omg.CORBA.ORB orb = null;
16
17         try
18         {
19             orb = org.omg.CORBA.ORB.init(args, props);
20             status = run(orb);
21         }
22         catch(Exception ex)
23         {
24             ex.printStackTrace();
25             status = 1;
26         }
27
28         if(orb != null)
29         {
30             try
31             {
32                 orb.destroy();
33             }
34             catch(Exception ex)
35             {
36                 ex.printStackTrace();
37                 status = 1;
38             }
39         }
40
41         System.exit(status);
42     }
```

Lines 8-12 These properties are necessary to use the Orbacus ORB instead of the JDK's ORB.

Line 19 The ORB must be initialized using `ORB.init`. The ORB class resides in the package `org.omg.CORBA`. You must either import this package, or, as shown in this example, you must use `org.omg.CORBA` explicitly.

Line 20 The `run()` helper function is called.

Lines 22-26 This code catches and prints all CORBA exceptions raised by `ORB.init()` or `run()`.

Lines 28-39 If the ORB was successfully created, it is destroyed. This releases the resources used by the ORB. If `destroy()` raises a CORBA exception, this exception is caught and printed.

Line 41 The exit status is returned. If there was no error, 0 is returned, or 1 otherwise.

Server class run() method

Add the run() method to Server.java:

```
1 // Java
2 static int run(org.omg.CORBA.ORB orb)
3     throws org.omg.CORBA.UserException
4 {
5     org.omg.PortableServer.POA rootPOA =
6         org.omg.PortableServer.POAHelper.narrow(
7             orb.resolve_initial_references("RootPOA"));
8
9     org.omg.PortableServer.POAManager manager =
10        rootPOA.the_POAManager();
11
12    Hello_impl helloImpl = new Hello_impl();
13    Hello hello = helloImpl._this(orb);
14
15    try
16    {
17        String ref = orb.object_to_string(hello);
18        String refFile = "Hello.ref";
19        java.io.PrintWriter out = new java.io.PrintWriter(
20            new java.io.FileOutputStream(refFile));
21        out.println(ref);
22        out.close();
23    }
24    catch(java.io.IOException ex)
25    {
26        ex.printStackTrace();
27        return 1;
28    }
29
30    manager.activate();
31    orb.run();
32    return 0;
33 }
34 }
```

Lines 5-10 A reference to the Root POA is obtained using the ORB reference, and the Root POA is used to obtain a reference to its POA Manager.

Lines 12-23 A servant of type `Hello_impl` is created and is used to incarnate a CORBA object. The CORBA object is released automatically when it is not used anymore.

Lines 15-28 The object reference is stringified and written to a file.

Lines 30-31 The server enters its event loop to receive incoming requests.

Implementing the Client

Client.java

Save this to a file with the name `Client.java` in the directory `hello`:

```
1 // Java
2 package hello;
3
4 public class Client
5 {
6     public static void main(String args[])
7     {
8         ... // Same as for the server
9     }
10
11     static int run(org.omg.CORBA.ORB orb)
12     {
13         org.omg.CORBA.Object obj = null;
14         try
15         {
16             String refFile = "Hello.ref";
17             java.io.BufferedReader in = new
18 java.io.BufferedReader(
19                 new java.io.FileReader(refFile));
20             String ref = in.readLine();
21             obj = orb.string_to_object(ref);
22         }
23         catch(java.io.IOException ex)
24         {
25             ex.printStackTrace();
26             return 1;
27         }
28         Hello hello = HelloHelper.narrow(obj);
29
30         hello.say_hello();
31
32         return 0;
33     }
34 }
```

Lines 6-9 This code is the same as for the server.

Lines 14-26 The stringified object reference is read and converted to an object.

Line 28 The object reference is narrowed to a reference to a `Hello` object. A simple Java cast is not allowed here, because it is possible that the client will need to ask the server whether the object is really of type `Hello`.

Line 30 The `say_hello` operation is invoked, causing the server to print “Hello World!” on standard output.

Compiling

Steps

To compile the application:

1. Ensure that your `CLASSPATH` environment variable includes the current working directory as well as the Orbacus for Java classes (i.e the `OB.jar` file) as shown below:

Platform	Command
UNIX	<code>CLASSPATH=.:your_orbacus_directory/lib/OB.jar:\$CLASSPATH</code> <code>export CLASSPATH</code>
Windows	<code>set CLASSPATH=.;your_orbacus_directory\lib\OBE.jar;%CLASSPATH%</code>

Replace `your_orbacus_directory` with the name of the directory where Orbacus is installed.

2. To compile the implementation classes and the classes generated by the Orbacus IDL-to-Java translator, use `javac` (or the Java compiler of your choice):

```
javac hello/*.java
```

Running the Application

Steps

To run the application, complete the following steps:

1. Start the Hello World Java server by entering the following command in a command prompt:

```
java hello.Server
```

2. Start the Hello World Java client by entering the following command:

```
java hello.Client
```

Again, make sure that your `CLASSPATH` environment variable includes the `OBE.jar` file.

You might also want to use a C++ server together with a Java client (or vice versa). This is one of the primary advantages of using CORBA: if something is defined in CORBA IDL, the programming language used for the implementation is irrelevant. CORBA applications can talk to each other, regardless of the language they are written in.

Summary

What have we learned?

At this point, you might be inclined to think that this is the most complicated method of printing a string that you have ever encountered in your career as a programmer. At first glance, a CORBA-based approach may indeed seem complicated. On the other hand, think of the benefits this kind of approach has to offer. You can start the server and client applications on different machines with exactly the same results.

Regarding the communication between the client and the server, you don't have to worry about platform-specific methods or protocols at all, provided there is a CORBA ORB available for the platform and programming language of your choice. If possible, get some hands-on experience and start the server on one machine, the client on another¹. As you will see, CORBA-based applications run interchangeably in both local and network environments.

One last point to note: you likely won't be using CORBA to develop systems as simple as our Hello, World example. The more complex your applications become (and today's applications *are* complex), the more you will learn to appreciate having a high-level abstraction of your applications' key interfaces captured in CORBA IDL.

1. Note that after the startup of the server program, you must copy the stringified object reference (that is, the file `Hello.ref`) to the machine where the client program is to be run.

Where To Go From Here

Further Reading

To understand the remaining chapters of this manual, you *must* have read the CORBA specifications in [\[4\]](#), [\[5\]](#), and [\[6\]](#). You will not be able to understand the chapters that follow without a good understanding of CORBA in general, CORBA IDL and the IDL-to-C++ or IDL-to-Java mappings.

Generating Code with Orbacus

This chapter describes the Orbacus translators.

In this chapter

This chapter contains the following sections:

Orbacus Translators	page 52
Translating IDL to C++	page 53
Translating IDL to Java	page 57
Translating IDL to HTML	page 59
Translating IDL to RTF	page 60
The IDL-to-C++ Translator and the Interface Repository	page 63
Include Statements	page 64
Documenting IDL Files	page 65
Using javadoc	page 68

Orbacus Translators

Overview

Orbacus includes the following code generators, or *translators*:

<code>idl</code>	Translates IDL to C++
<code>jidl</code>	Translates IDL to Java
<code>hidl</code>	Translates IDL to HTML
<code>ridl</code>	Translates IDL to RTF
<code>irgen</code>	Generates C++ from an Interface Repository

Translating IDL to C++

Synopsis

```
idl [options] idl-files...
```

Description

Translates IDL files into C++ files.

For each IDL file four C++ files are generated. For example,

```
idl MyFile.idl
```

produces the following files:

MyFile.h	Header file containing MyFile.idl's translated data types and interface stubs
MyFile.cpp	Source file containing MyFile.idl's translated data types and interface stubs
MyFile_skel.h	Header file containing skeletons for MyFile.idl's interfaces
MyFile_skel.cpp	Source file containing skeletons for MyFile.idl's interfaces

Options

```
-h, --help
```

Show a short help message.

```
-v, --version
```

Show the Orbacus version number.

```
-d, --debug
```

Print diagnostic messages. This option is for Orbacus internal debugging purposes only.

```
-DNAME
```

Defines NAME as 1. This option is directly passed to the preprocessor.

```
-DNAME=DEF
```

Defines NAME as DEF. This option is directly passed to the preprocessor.

```
-UNAME
```

Removes any definition for NAME. This option is directly passed to the preprocessor.

```
-IDIR
```

- Adds the directory `DIR` to the include file search path. This option is directly passed to the preprocessor.
- `-E`
Runs the source files through the preprocessor without generating code.
- `--no-skeletons`
Don't generate skeleton classes.
- `--no-type-codes`
Don't generate type codes and insertion and extraction functions for the Any type. Use of this option will cause the translator to generate more compact code.
- `--no-virtual-inheritance`
Don't use virtual C++ inheritance. If you use this option, you cannot use multiple interface inheritance in your IDL code, and you also cannot use multiple C++ inheritance to implement your servant classes.
- `--tie`
Generate tie classes for delegate-based interface implementations. Tie classes depend on the corresponding skeleton classes. That is, you must not use `--no-skeletons` in combination with `--tie`.
- `--fwd`
Generate separate header files for forward declarations.
- `--impl`
Generate example servant implementation classes. An input file `Foo.idl` will generate the files `Foo_impl.h` and `Foo_impl.cpp`. These files will not be overwritten, therefore you must first remove the existing files before new ones can be generated. You must not use `--no-skeletons` in combination with this option.
- `--impl-all`
Similar to `--impl`, but function signatures are generated for all inherited operations and attributes. You must not use `--no-skeletons` in combination with this option.
- `--c-suffix SUFFIX`
Use `SUFFIX` as the suffix for source files. The default value is `.cpp`.
- `--h-suffix SUFFIX`
Use `SUFFIX` as the suffix for header files. The default value is `.h`.

`--stub-suffix SUFFIX`
Use `SUFFIX` as the suffix for stub files. The default value is an empty suffix.

`--skel-suffix SUFFIX`
Use `SUFFIX` as the suffix for skeleton files. The default value is `_skel`.

`--all`
Generate code for included files instead of inserting `#include` statements. See [“Include Statements” on page 64](#).

`--no-relative`
When generating code, `idl` assumes that the same `-I` options that are used with `idl` are also going to be used with the C++ compiler. Therefore `idl` will try to make all `#include` statements relative to the directories specified with `-I`. The option `--no-relative` suppresses this behavior, in which case `idl` will not make `#include` statements for included files relative to the paths specified with the `-I` option.

`--header-dir DIR`
This option can be used to make `#include` statements for header files relative to the specified directory.

`--this-header-dir DIR`
Like the `--header-dir` option, this option can be used to make `#include` statements for header files relative to the specified directory. However, this option only applies to `#include` statements for the header files of this IDL file.

`--other-header-dir DIR`
Like the `--header-dir` option, this option can be used to make `#include` statements for header files relative to the specified directory. However, this option only applies to `#include` statements for the header files corresponding to IDL files that were included in this IDL file.

`--output-dir DIR`
Write generated files to directory `DIR`.

`--file-list FILE`
Write a list of all generated files to file `FILE`.

`--dll-import DEF`
Put `DEF` in front of every symbol that needs an explicit DLL import statement.

`--with-interceptor-args`

Generate code with support for arguments, result and exception list values for interceptors.

`--no-local-copy`

To ensure strict compliance with CORBA's location transparency semantics, the default behavior of the translator is to generate code that copies valuetype argument and result values for collocated invocations. Specify this option to disable strict compliance and generate more efficient code.

`--case-sensitive`

The semantics of OMG IDL forbid identifiers in the same scope to differ only in case. This option relaxes these semantics, but is only provided for backward compatibility with non-compliant IDL.

`--with-async`

Generate code with support for Asynchronous Method Invocation (AMI).

Translating IDL to Java

Synopsis

```
jidl [options] idl-files...
```

Description

Translates IDL files into Java files.

For every construct in the IDL file that maps to a Java class or interface, a separate class file is generated. Directories are automatically created for those IDL constructs that map to a Java package (for example, a `module`).

`jidl` can also add comments from the IDL file starting with `/**` to the generated Java files. This allows you to use the `javadoc` tool to produce documentation from the generated Java files. See [“Using javadoc” on page 68](#) for additional information.

Options for jidl

```
-h, --help
-v, --version
-d, --debug
-DNAME
-DNAME=DEF
-UNAME
-IDIR
-E
--no-skeletons
--locality-constrained
--all
--tie
--file-list FILE
--no-local-copy
--case-sensitive
--with-async
```

These options are the same as for the `idl` command.

```
--no-comments
```

The default behavior of `jidl` is to add any comments from the IDL file starting with `/**` to the generated Java files. Specify this option if you don't want these comments added to your Java files.

```
--package PKG
```

Specifies a package name for the generated Java classes. Each class will be generated relative to this package.

- `--prefix-package PRE PKG`
Specifies a package name for a particular prefix¹. Each class with this prefix will be generated relative to the specified package.
- `--auto-package`
Derives the package names for generated Java classes from the IDL prefixes. The prefix `ooc.com`, for example, results in the package `com.ooc`.
- `--output-dir DIR`
Specifies a directory where `jidl` will place the generated Java files. Without this option the current directory is used.
- `--clone`
Generates a `clone` method for struct, union, enum, exception, valuetype and abstract interface types. For valuetypes, only an abstract method is generated. The valuetype implementer must supply an implementation for `clone`.
- `--impl`
Generates example servant implementation classes. For IDL interface types, a class is generated in the same package as the interface classes, having the same name as the interface with the suffix `_impl`. The generated class extends the POA class of the interface. For IDL valuetypes, a class is generated in the same package as the valuetype with the suffix `ValueFactory_impl`. You must not use `--no-skeletons` in combination with this option.
- `--impl-tie`
Similar to `--impl`, but implementation classes for interfaces implement the `Operations` interface to facilitate the use of TIE classes. You must not use `--no-skeletons` in combination with this option.
- `--with-interceptor-args`
Generate code with support for arguments, result and exception list values for interceptors. Note that use of this option will generate proprietary stubs and skeletons which are not compatible with ORBs from other vendors.

1. Prefix refers to the value of the `#pragma prefix` statement in an IDL file. For example, the statement `#pragma prefix "ooc.com"` defines `ooc.com` as the prefix. The prefix is included in the Interface Repository identifiers for all types defined in the IDL file.

Translating IDL to HTML

Synopsis

```
hidl [options] idl-files...
```

Description

Creates HTML files from IDL files.

An HTML file is generated for each module and interface defined in an IDL file. Comments in the IDL file are preserved and `javadoc` style keywords are supported. The section [“Documenting IDL Files” on page 65](#) provides more information.

Options for hidl

```
-h, --help  
-v, --version  
-d, --debug  
-DNAME  
-DNAME=DEF  
-UNAME  
-IDIR  
--all  
--case-sensitive
```

These options are the same as for the `idl` command.

```
--no-sort
```

Don't sort symbols alphabetically.

```
--ignore-case
```

Sort case-insensitive.

```
--use-tables
```

Use tables for indices.

```
--alt-indent
```

Use alternative indentation for argument lists. The alternative format requires less horizontal space, which is in particular useful if the names of the operation or arguments are long.

```
--output-dir DIR
```

Write HTML files to the directory `DIR`.

Translating IDL to RTF

Description

`ridl` creates Rich Text Format (RTF) files from IDL files. An RTF file is generated for each module and interface defined in an IDL file. Comments in the IDL file are preserved and `javadoc` style keywords are supported. The section [“Documenting IDL Files” on page 65](#) provides more information.

Options for `ridl`

```
-h, --help
-v, --version
-d, --debug
-DNAME
-DNAME=DEF
-UNAME
-IDIR
--all
--case-sensitive
```

These options are the same as for the `idl` command.

```
--no-sort
--ignore-case
--use-tables
--alt-indent
```

These options are the same as for the `hidl` command.

```
--output-dir DIR
```

Write RTF files to the directory `DIR`.

```
--single-file FILE
```

Create a single file called `FILE.rtf`.

```
--with-index
```

Create index entries.

```
--font PARA NAME
```

```
--font-size PARA SIZE
```

Specify the font name or size for a particular paragraph type. The paragraph types and their default values are shown below.

Type	Font	Size
body	roman Times New Roman	12 pt

Type	Font	Size
entry	swiss Tahoma	12 pt
extra	<i>same as body</i>	12 pt
heading	swiss Arial	18 pt
index	<i>same as heading</i>	15 pt
literal	roman Courier New	10 pt
symbol	roman Symbol	12 pt

Generating C++ from an Interface Repository

Synopsis

```
irgen name-base
```

Description

`irgen` generates C++ code directly from the contents of an Interface Repository. See [“The IDL-to-C++ Translator and the Interface Repository” on page 63](#) for an example.

Options for irgen

```
-h, --help
-v, --version
--no-skeletons
--no-type-codes
--locality-constrained
--no-virtual-inheritance
--tie
--impl
--impl-all
--c-suffix SUFFIX
--h-suffix SUFFIX
--skel-suffix SUFFIX
--header-dir DIR
--other-header-dir DIR
--output-dir DIR
--file-list FILE
--dll-import DEF
--with-interceptors-args
--no-local-copy
```

These options are the same as for the `idl` command.

The argument to `irgen` is the pathname to use as the base name of the output filenames. For example, if the pathname you supply is `output/file`, then `irgen` will produce `output/file.cpp`, `output/file.h`, `output/file_skel.cpp` and `output/file_skel.h`.

Note that `irgen` will generate code for *all* of the type definitions contained in the Interface Repository server.

See [Chapter 13](#) for more information on the Interface Repository.

The IDL-to-C++ Translator and the Interface Repository

Private Versus Global Interface Repositories

The Orbacus IDL-to-C++ and IDL-to-Java translators internally use the Interface Repository for generating code. That is, these programs have their own private Interface Repository that is fed with the specified IDL files. All code is generated from that private Interface Repository.

However it is also possible to generate C++ code from a global Interface Repository.

Steps

To generate C++ code from a global Interface Repository:

1. Start the Interface Repository using the command `irserv`.
2. Feed the Interface Repository the IDL code, using the command `irfeed`.
3. Finally, use the `irgen` command to generate the C++ code.

Example

For example:

```
irserv --ior > IntRep.ref &
irfeed -ORBrepository 'cat IntRep.ref' file.idl
irgen -ORBrepository 'cat IntRep.ref' file
```

By comparison, the IDL-to-C++ translator `idl` performs all these steps at once, in a single process using a private Interface Repository. Thus, you only have to run a single command:

```
idl file.idl
```

See [Chapter 13](#) for more information on the Interface Repository.

Include Statements

Using `#include` statements

If you use the `#include` statement in your IDL code, the Orbacus IDL-to-C++ translator `idl` does not create code for included IDL files. Instead, the translator inserts the appropriate `#include` statements in the generated header files.

Restrictions

There are several restrictions on where to place the `#include` statements in your IDL files for this feature to work properly:

- `#include` may only appear at the beginning of your IDL files. All `#include` statements must be placed before the rest of your IDL code.¹
- Type definitions, such as `interface` or `struct` definitions, may not be split among several IDL files. In other words, no `#include` statement may appear within such definitions.

If you do not want these restrictions to be applied, you can use the translator option `--all` with `idl`. With this option, the IDL-to-C++ translator treats code from included files as if the code appeared in your IDL file at the position where it is included. This means that the compiler will not place `#include` statements in the automatically-generated header files, regardless of whether the code comes directly from your IDL file or from files included by your IDL file.

Note that when generating code from an Interface Repository using `irgen`, the translator behaves identically to `idl` with the `--all` option. In other words, the `irgen` command does not place `#include` statements in the generated files, but rather generates code for all IDL definitions in the Interface Repository.

1. Preprocessor statements like `#define` or `#ifdef` may be placed before your `#include` statements.

Documenting IDL Files


Overview

With the Orbacus IDL-to-HTML and IDL-to-RTF translators, `hidl` and `ridl`, you can easily generate HTML and RTF files containing IDL interface descriptions. The translators generate a nicely-formatted file for each IDL module and interface.

Example

Figure 1 shows an HTML example:

Figure 1: *Documentation generated with the IDL-to-HTML translator*

**Syntax**

The formatting syntax supported by `hidl` and `ridl` is similar to that used by `javadoc`. The following keywords are recognized:

```
@author author
```

Denotes the author of the interface.

`@exception exception-name description`

Adds an exception description to the exception list of an operation.

`@member member-name description`

Adds a member description to the member list of a struct, union, enum or exception type.

`@param parameter-name description`

Adds a parameter description to the parameter list of an operation.

`@return description`

Adds descriptive text for the return value of an operation.

`@see reference`

Adds a See also note.

`@since since-text`

Comment related to the availability of new features.

`@version version`

The interface's version number.

Like `javadoc`, `hidl` and `ridl` use the first sentence in the documentation comment as the summary sentence. This sentence ends at the first period that is followed by a blank, tab or line terminator, or at the first `@`.

`ridl` understands most basic HTML tags and produces an equivalent format in the generated RTF files. The following HTML tags are supported:

`` `
` `<CODE>` `<DD>` `<DL>` `<DT>` `` `<HR>` `<I>` `` `` `<P>` `<TABLE>`
`<TD>` `<TR>` `<U>` ``

Using javadoc

Adding IDL Comments

If not explicitly suppressed with the `--no-comments` option, the Orbacus IDL-to-Java translator `jidl` adds IDL comments starting with `/**` to the generated Java files, so that `javadoc` can be used to generate documentation (as long as the comments are in a format compatible with `javadoc`).

Example

Here is an example that shows how to include documentation in an IDL interface description file. Let's assume we have an interface `I` in a module `M`:

```
// IDL

module M
{

/**
 *
 * This is a comment related to interface I.
 *
 * @author Uwe Seimet
 *
 * @version 1.0
 *
 */
interface I
{

/**
 *
 * This comment describes exception E.
 *
 */
exception E { };
}
```

```

/**
 *
 * The description for operation S.
 *
 * @param arg A dummy argument.
 *
 * @return A dummy string.
 *
 * @exception E Raised under certain circumstances.
 *
 */
string S(in long arg)
    raises (E);
};
};

```

When running `jid1` on this file, the comments are automatically added to the generated Java files `M/I.java` and `M/IPackage/E.java`. For `I.java`, the generated code looks as follows:

```

// Java

package M;

//
// IDL:M/I:1.0
//
/**
 * This is a comment related to interface I.
 *
 * @author Uwe Seimet
 *
 * @version 1.0
 *
 */

```

```

public interface I extends org.omg.CORBA.Object
{
    //
    // IDL:M/I/S:1.0
    //
    /**
     *
     * The description for operation S.
     *
     * @param arg A dummy argument.
     *
     * @return A dummy string.
     *
     * @exception M.IPackage.E Raised under certain
    circumstances.
     *
     **/
    public String
    S(int arg)
        throws M.IPackage.E;
}

```

Note that `jidl` automatically inserts the fully-qualified Java name for the exception `E` (`M.IPackage.E` in this case).

These are the contents of `IPackage/E.java`:

```

// Java

package M.IPackage;

//
// IDL:M/I/E:1.0
//
/**
 *
 * This comment describes exception E.
 *
 **/
final public class E extends org.omg.CORBA.UserException
{
    public
    E()
    {
    }
}

```

Now you can use `javadoc` to extract the comments from the generated Java files and produce nicely-formatted HTML documentation.

For additional information please refer to the `javadoc` documentation.

ORB and Object Adapter Initialization

This chapter describes the initialization of client and server ORBs in various languages.

In this chapter

This chapter contains the following sections:

Initializing the C++ ORB	page 74
Initializing the Java ORB	page 75
Object Adapter Initialization	page 76
Configuring the ORB and Object Adapter	page 77
Using POA Managers	page 97
ORB Destruction	page 108
Server Event Loop	page 109

Initializing the C++ ORB

In C++, the ORB is initialized with `CORBA::ORB_init()`. For example:

```
// C++
int main(int argc, char* argv[])
{
    CORBA::ORB_var orb = CORBA::ORB_init(argc, argv);
    // ...
}
```

The `CORBA::ORB_init()` call interprets arguments starting with `-ORB` and `-OA`. All of these arguments, passed through the `argc` and `argv` parameters, are automatically removed from the argument list.

Initializing the Java ORB

The ORB implementation included in JDK 1.3 and newer can be considered a minimal ORB, suitable primarily for use in basic client-oriented tasks. In order to use the Orbacus ORB instead of the JDK's default ORB, you must start your application with the following properties:

```
java -Dorg.omg.CORBA.ORBClass=com.ooc.CORBA.ORB \  
     -Dorg.omg.CORBA.ORBSingletonClass=com.ooc.CORBA.ORBSingleton \  
     MyApp
```

An alternative is to set these properties in your program before initializing the ORB. For example:

```
// Java  
import org.omg.CORBA.*;  
public static void main(String args[])  
{  
    java.util.Properties props = System.getProperties();  
    props.put("org.omg.CORBA.ORBClass", "com.ooc.CORBA.ORB");  
    props.put("org.omg.CORBA.ORBSingletonClass",  
             "com.ooc.CORBA.ORBSingleton");  
  
    ORB orb = ORB.init(args, props);  
    // ...  
}
```

The `ORB.init()` call interprets arguments starting with `-ORB` and `-OA`. Unlike the C++ version, these arguments are not removed (see [“Advanced Property Usage” on page 95](#) for more information).

Object Adapter Initialization

In Orbacus, the object adapter is not initialized until the Root POA is first resolved. For example:

```
// C++
CORBA::Object_var poaObj =
    orb -> resolve_initial_references("RootPOA");
```

```
// Java
org.omg.CORBA.Object poaObj =
    orb.resolve_initial_references("RootPOA");
```

Upon completion, the ORB will have created the Root POA and its POA Manager, and will have initialized the ORB's server-side functionality.

Configuring the ORB and Object Adapter

Overview

Orbacus applications can tailor the behavior of the ORB and object adapters using a collection of properties. These properties can be defined in a number of ways:

- using the Windows Registry (Windows C++)
- using a configuration file
- using system properties (Java)
- using command-line options
- programmatically at run-time

The Orbacus configuration properties are described in the following sections. Unless otherwise noted, every property can be used in both C++ and Java applications.

Note: The properties described in this section have nothing to do with the Property Service, as described in [Appendix B](#).

In this section

This section contains the following subsections:

ORB Properties	page 78
OA Properties	page 85
Command-line Options	page 88
Using a Configuration File	page 90
Using the Windows Registry	page 91
Defining Properties	page 92
Precedence of Properties	page 94
Advanced Property Usage	page 95

ORB Properties

ooc.configValue: *filename*

Selects the default configuration file. This property is only available in Java applications and is equivalent to the `ORBACUS_CONFIG` environment variable in C++. See [“Using a Configuration File” on page 90](#) for more information on configuration files.

ooc.oci.clientValue: *string*

Specifies a comma-separated list of client-side transport plug-ins to be installed. The plug-ins are installed in the order they appear in the list. The default value is `iiop`.

ooc.oci.serverValue: *string*

Specifies a comma-separated list of server-side transport plug-ins to be installed. The plug-ins are installed in the order they appear in the list. The default value is `iiop`.

ooc.oci.plugin.nameValue: *string*

Specifies a plug-in’s shared library (C++) or initialization class (Java). In most cases this property is not necessary because the ORB attempts to locate the library or class using a well-known name. In C++, the well-known name is `libOCI_name.so` (UNIX), `libOCI_name.sl` (HP-UX) or `OCI_name.dll` (Windows), where *name* is the plug-in name (for example, `iiop`). The ORB searches for this shared library in the library search path. Similarly, in Java the ORB searches the class path for a class named `com.ooc.OCI.name`.

ooc.orb.client_shutdown_timeoutValue: *timeout* ≥ 0

If the client is not able to gracefully disconnect from the server in *timeout* seconds, a connection shutdown is forced. If this property is set to zero, then the client will not force a connection shutdown. If the property is not set, a default timeout value of two seconds is used.

ooc.orb.client_timeout	<p>Value: <i>timeout</i> ≥ 0</p> <p>The client actively closes a connection that has been idle for <i>timeout</i> seconds once that connection has no more outstanding replies. Note that the application must use the threaded client-side concurrency model if connection timeouts are desired. If this property is set to zero, or not set at all, then the client does not close idle connections. Note that a policy can also be set on the ORB or on individual object references. See “OB::ACMTimeoutPolicy” on page 331 for more information.</p>
ooc.orb.conc_model	<p>Value: <i>reactive, threaded</i></p> <p>Selects the client-side concurrency model. The reactive concurrency model is not currently available in Orbacus for Java. The default value is <i>threaded</i> for both C++ and Java applications. See Chapter 18 for more information on concurrency models.</p>
ooc.orb.default_init_ref	<p>Value: <i>URL</i></p> <p>Specifies a partial URL. If an application calls the ORB operation <code>resolve_initial_references</code> and no match is found, the ORB appends a slash (<code>'/'</code>) character and the service identifier to the specified URL and invokes <code>string_to_object</code> to obtain the initial reference.</p>
ooc.orb.default_wcs	<p>Value: <i>string</i></p> <p>Specifies the default wide character code set for the ORB. Note that the CORBA specification states that a default wide character code set does not exist. Therefore, this option should only be used when communicating with a broken ORB that expects a particular wide character code set and does not correctly support the negotiation of wide character code sets.</p>
ooc.orb.extended_wchar	<p>Value: <i>true, false</i></p> <p>Enables transfers of wide characters (IDL types <code>wchar</code> and <code>wstring</code>) with IOP 1.0, using Unicode as the code set. This proprietary extension is required in order to exchange wide characters with Orbix/E, which only supports IOP 1.0. The default is <i>false</i>.</p>
ooc.orb.giop.max_message_size	<p>Value: <i>max</i> ≥ 0</p>

Specifies the maximum GIOP message size in bytes. If set to 0, no maximum message size will be used. If a message is sent or received that exceeds the maximum size, the ORB will raise the `IMP_LIMIT` system exception.

ooc.orb.id

Value: *id*

Specifies the identifier of the ORB to be used by the application.

ooc.orb.modules

Value: *string*

Specifies a comma-separated list of modules to be loaded dynamically by the ORB. The ORB locates the shared library for a module using a well-known name: `libname.so` (UNIX), `libname.sl` (HP-UX) or `name.dll` (Windows), where *name* is the module name. The ORB then invokes the initialization function `init_module_name` in that shared library. The initialization function takes no arguments and returns `void`. A module initialization function will typically register an ORBInitializer, which allows interceptors and initial references to be installed. This property is only supported in C++. In Java, the standard mechanism for installing an ORBInitializer should be used. See [7] for more information on ORBInitializers.

ooc.orb.module.name

Value: *string*

Specifies the name of a module's shared library or DLL. In most cases this property is not necessary because the ORB attempts to locate the library using a well-known name, as described above for the `ooc.orb.modules` property. The value of this property can be a simple filename, in which case the ORB will attempt to load the library using the search path, or it can be an absolute pathname.

ooc.orb.native_cs

Value: *string*

Specifies the native character code set for the ORB. The default is ISO 8859-1.

ooc.orb.native_wcs

Value: *string*

Specifies the native wide character code set for the ORB. The default is UTF-16.

ooc.orb.policy.connect_timeout	Value: <i>timeout</i> ≥ -1 Sets the <code>OB::ConnectTimeoutPolicy</code> at the ORB level. See Appendix B for more information on this policy. The default value is <code>-1</code> .
ooc.orb.policy.connection_reuse	Value: <code>true</code> , <code>false</code> Sets the <code>OB::ConnectionReusePolicy</code> at the ORB level. See Appendix B for more information on this policy. The default value is <code>true</code> .
ooc.orb.policy.interceptor	Value: <code>true</code> , <code>false</code> Sets the <code>OB::InterceptorPolicy</code> at the ORB level. See Appendix B for more information on this policy. The default value is <code>true</code> .
ooc.orb.policy.locate_request	Value: <code>true</code> , <code>false</code> Sets the <code>OB::LocateRequestPolicy</code> at the ORB level. See Appendix B for more information on this policy. The default value is <code>false</code> .
ooc.orb.policy.location_transparency	Value: <code>strict</code> , <code>relaxed</code> Sets the <code>OB::LocationTransparencyPolicy</code> at the ORB level. See Appendix B for more information on this policy. The default value is <code>relaxed</code> .
ooc.orb.policy.protocol	Value: <i>string</i> Sets the <code>OB::ProtocolPolicy</code> at the ORB level. See Appendix B for more information on this policy.
ooc.orb.policy.rebind	Value: <code>transparent</code> , <code>no_rebind</code> , <code>no_reconnect</code> Sets the <code>Messaging::RebindPolicy</code> at the ORB level. The default value is <code>transparent</code> .
ooc.orb.policy.request_timeout	Value: <i>timeout</i> ≥ -1 Sets the <code>OB::RequestTimeoutPolicy</code> at the ORB level. See Appendix B for more information on this policy. The default value is <code>-1</code> .

ooc.orb.policy.retry	<p>Value: <i>never, strict, always</i></p> <p>Sets the <code>mode</code> attribute of the <code>OB::RetryPolicy</code> at the ORB level. See Appendix B for more information on this policy. The default value is <code>strict</code>.</p>
ooc.orb.policy.retry.interval	<p>Value: <i>timeout >= 0</i></p> <p>Sets the <code>interval</code> attribute of the <code>OB::RetryPolicy</code> at the ORB level. See Appendix B for more information on this policy. The default value is <code>0</code>.</p>
ooc.orb.policy.retry.max	<p>Value: <i>timeout >= 0</i></p> <p>Sets the <code>max</code> attribute of the <code>OB::RetryPolicy</code> at the ORB level. See Appendix B for more information on this policy. The default value is <code>1</code>.</p>
ooc.orb.policy.retry.remote	<p>Value: <i>true, false</i></p> <p>Sets the <code>remote</code> attribute of the <code>OB::RetryPolicy</code> at the ORB level. See Appendix B for more information on this policy. The default value is <code>false</code>.</p>
ooc.orb.policy.sync_scope	<p>Value: <i>none, transport, server, target</i></p> <p>Sets the <code>Messaging::SyncScopePolicy</code> at the ORB level. The default value is <code>transport</code>.</p>
ooc.orb.policy.timeout	<p>Value: <i>timeout >= -1</i></p> <p>Sets the <code>OB::TimeoutPolicy</code> at the ORB level. See Appendix B for more information on this policy. The default value is <code>-1</code>.</p>
ooc.orb.raise_dii_exceptions	<p>Value: <i>true, false</i></p> <p>Determines whether system exceptions that occur during Dynamic Invocation Interface (DII) operations are raised immediately or are stored only in the <code>CORBA::Environment</code> object. This property is only available for Java applications. The default value is <code>true</code>. Note that specifying a value of <code>false</code> may result in unexpected behavior.</p>
ooc.orb.server_name	<p>Value: <i>string</i></p>

Specifies the name of the server, as registered with the Implementation Repository (IMR). Note that you should not put this property in a configuration file that is shared by several IMR-enabled servers. Furthermore, this property should not be specified for servers that are not registered with the IMR.

ooc.orb.server_shutdown_timeout

Value: *timeout* ≥ 0

If the server is not able to gracefully disconnect from the client in *timeout* seconds, a connection shutdown is forced. If this property is set to zero, then the server will not force a connection shutdown. If the property is not set, a default timeout value of two seconds is used.

ooc.orb.server_timeout

Value: *timeout* ≥ 0

The server actively closes a connection that has been idle for *timeout* seconds once that connection has no more outstanding replies. Note that the application must use one of the threaded server-side concurrency model if connection timeouts are desired. If this property is set to zero, or not set at all, then the server does not close idle connections.

ooc.orb.use_type_code_cache

Value: `true`, `false`

Determines whether the ORB caches TypeCodes. When the TypeCode cache is disabled, the ORB creates a new TypeCode object for each TypeCode received over the wire, including those associated with Any values. When the TypeCode cache is enabled, only one TypeCode object is instantiated for each TypeCode with a unique, non-empty repository id. The default value is `true`.

Note that there is one rare case where the cache may not work as expected: if an application requires the received TypeCode to be equal to the one that was transmitted, where equal implies a successful result from the `TypeCode::equal()` operation. Although TypeCodes with the same repository id are always equivalent, they are not always equal because of TypeCode compaction. However, if the cache is enabled, two TypeCode objects received over the wire with the same repository id will always be equal. For more information on the semantics of the `equal()` and `equivalent()` TypeCode operations, see [\[3\]](#).

ooc.orb.service.name

Value: *ior*

Adds an initial service to the ORB's internal list. This list is consulted when the application invokes the ORB operation `resolve_initial_references`. `name` is the key that is associated with an IOR or URL. For example, the property `ooc.orb.service.NameService` adds `NameService` to the list of initial services. See [“The BootManager” on page 166](#) for more information.

ooc.orb.trace.connections

Value: *level* ≥ 0

Defines the output level for diagnostic messages printed by Orbacus that are related to connection establishment and closure. A level of 1 or higher produces information about connection events, and a level of 2 or higher produces code set exchange information. The default level is 0, which produces no output.

ooc.orb.trace.retry

Value: *level* ≥ 0

Defines the output level for diagnostic messages printed by Orbacus that are related to transparent re-sending of failed messages. A level of 1 or higher produces information about re-sending of messages, and a level of 2 or higher also produces information about use of individual IOR profiles. The default level is 0, which produces no output.

OA Properties

Overview

Configuring an object adapter is achieved by setting properties on POA Managers. These properties are grouped into two categories: global properties, and properties specific to a particular POA Manager. Global properties have the prefix `ooc.orb.ora`, while properties specific to a particular POA Manager have the prefix `ooc.orb.poamanager.name`, where *name* is the name of the POA Manager (see [“Using POA Managers” on page 97](#)).

Unless otherwise noted, a POA Manager will search for configuration properties using the following algorithm:

- First, use properties defined specifically for that POA Manager
- Next, use global properties
- Finally, use default settings.

See [“Using POA Managers” on page 97](#) for more information on POA Managers.

`ooc.orb.ora.conc_model`

Value: `reactive`, `threaded`, `thread_per_client`, `thread_per_request`, `thread_pool`, `leader_follower`

Selects the server-side concurrency model. The default value is `thread_per_client`. The `reactive` and `leader_follower` concurrency models are only available in Orbacus for C++. See [Chapter 18](#) for more information on concurrency models.

If this property is set to `thread_pool`, then the property `ooc.orb.ora.thread_pool` determines how many threads are in the pool.

If this property is set to `leader_follower`, then the property `ooc.orb.ora.leader_follower_pool` determines how many threads are to be used.

This property is also used to determine the default value of the communications concurrency model for POA Managers (see `ooc.orb.poamanager.manager.conc_model` below). The following table summarises how the setting of this property determines the POA Manager defaults:

Table 1: *POA Managers' Communications Concurrency Model*

Value of <code>ooc.orb.oe.conc_model</code>	<code>ooc.orb.poamanager.<manager>.conc_model</code> default
reactive	reactive
leader_follower	leader_follower
threaded	threaded
thread_per_client	threaded
thread_per_request	threaded
thread_pool	threaded

`ooc.orb.oe.endpoint`

Value: *string*

Specifies a comma-separated list of endpoints for the Root POA Manager. The default value is `iiop`. See [“Endpoints” on page 104](#) for more information.

`ooc.orb.oe.leader_follower_pool`

Value: *n > 0*

Determines the number of threads in the pool used by the `leader_follower` concurrency model. The default value is 10. This property is only effective when the `ooc.orb.oe.conc_model` property has the value `leader_follower`.

`ooc.orb.oe.thread_pool`

Value: *n > 0*

Determines the number of threads to reserve for servicing incoming requests. The default value is 10. This property is only effective when the `ooc.orb.oe.conc_model` property has the value `thread_pool`.

`ooc.orb.oe.version`

Value: 1.0, 1.1 or 1.2

Specifies the GIOP version to be used in object references. The default value is 1.2. This option is useful for backward compatibility with older ORBs that reject object references using a newer version of the protocol.

**ooc.orb.poamanager.manager.
conc_model**

Value: reactive, threaded

Specifies the communications concurrency model used by the POA Manager with name *manager*. The default value is determined by `ooc.orb.oa.conc_model`. See [Chapter 18](#) for more information on concurrency models.

**ooc.orb.poamanager.manager.
endpoint**

Value: *string*

Specifies a comma-separated list of endpoints for the POA Manager with name *manager*. The default value is `iiop`. See [“Endpoints” on page 104](#) for more information.

**ooc.orb.poamanager.manager.
leader_follower_pool**

Value: $n > 0$

Determines the number of threads in the pool used by the `leader_follower` concurrency model. The default value is 10. This property is only effective when the `ooc.orb.poamanager.manager.conc_model` property has the value `leader_follower`.

**ooc.orb.poamanager.manager.
version**

Value: 1.0, 1.1 or 1.2

Specifies the GIOP version to be used in object references generated by a particular POA Manager. This option is useful for backward compatibility with older ORBs that reject object references using a newer version of the protocol. The default value is determined by the value of `ooc.orb.oa.version`.

Command-line Options

There are equivalent command-line options for many of the Orbacus properties. The options and their equivalent property settings are shown in the following table. Refer to [“ORB Properties” on page 78](#) for a description of the properties.

Option	Property
-OAreactive	<code>ooc.orb.oe.conc_model=reactive</code>
-OAtthreaded	<code>ooc.orb.oe.conc_model=threaded</code>
-OAtthread_per_client	<code>ooc.orb.oe.conc_model=thread_per_client</code>
-OAtthread_per_request	<code>ooc.orb.oe.conc_model=thread_per_request</code>
-OAtthread_pool <i>n</i>	<code>ooc.orb.oe.conc_model=thread_pool</code> <code>ooc.orb.oe.thread_pool=<i>n</i></code>
-OAlleader_follower <i>n</i>	<code>ooc.orb.oe.conc_model=leader_follower</code> <code>ooc.orb.oe.leader_follower_pool=<i>n</i></code>
-OAversion <i>version</i>	<code>ooc.orb.oe.version=<i>version</i></code>
-ORBDefaultInitRef <i>URL</i>	<code>ooc.orb.default_init_ref=<i>URL</i></code>
-ORBid <i>id</i>	<code>ooc.orb.id=<i>id</i></code>
-ORBInitRef <i>name=ior</i>	<code>ooc.orb.service.name=<i>ior</i></code>
-ORBnative_cs <i>name</i>	<code>ooc.orb.native_cs=<i>name</i></code>
-ORBnative_wcs <i>name</i>	<code>ooc.orb.native_wcs=<i>name</i></code>
-ORBnaming <i>ior</i>	<code>ooc.orb.service.NameService=<i>ior</i></code>
-ORBproperty <i>name=value</i>	<code><i>name=value</i></code>
-ORBreactive	<code>ooc.orb.conc_model=reactive</code>
-ORBrepository <i>ior</i>	<code>ooc.orb.service.InterfaceRepository=<i>ior</i></code>
-ORBServerId <i>string</i>	<code>ooc.orb.server_name=<i>string</i></code>
-ORBservice <i>name ior</i>	<code>ooc.orb.service.name=<i>ior</i></code>

Option	Property
-ORBthreaded	ooc.orb.conc_model=threaded
-ORBtrace_connections <i>level</i>	ooc.orb.trace.connections= <i>level</i>
-ORBtrace_retry <i>level</i>	ooc.orb.trace.retry= <i>level</i>

A few additional command-line options are supported that do not have equivalent properties. These options are described in the following table.

Option	Description
-ORBconfig <i>filename</i>	Causes the ORB to load the configuration file specified by <i>filename</i> .
-ORBversion	Causes the ORB to print its version to standard output.

Using a Configuration File

A convenient way to define a group of properties is to use a configuration file. A sample configuration file is shown below:

```
# Concurrency models
ooc.orb.conc_model=threaded
ooc.orb.oa.conc_model=thread_pool
ooc.orb.oa.thread_pool=5

# Initial services
ooc.orb.service.NameService=corbaloc::myhost:7000/NameService
ooc.orb.service.EventService=corbaloc::myhost:7001/
  DefaultEventChannel
ooc.orb.service.TradingService=corbaloc::myhost:7002/
  TradingService
```

Note that trailing blanks are *not* ignored but are a part of the property.

You can define the name of the configuration file¹ using a command-line option, an environment variable (C++), or a system property (Java):

- Command-line option:
-ORBconfig *filename*
- Environment variable:
ORBACUS_CONFIG=*filename*
- Java system property:
ooc.config=*filename*

When an ORB is initialized, it first checks for the presence of the environment variable or system property. If present, the ORB loads the configuration file. Next, the ORB loads the configuration file specified by the -ORBconfig option. Therefore, the properties loaded from the file specified by -ORBconfig will override any existing properties, including those loaded by a configuration file specified in the environment variable or system property. See [“Precedence of Properties” on page 94](#) for more information.

Configuration files are only loaded during ORB initialization. Changes made to a configuration file after an ORB has been initialized have no effect on that ORB.

1. Orbacus for Java also accepts a URL specification as the filename.

Using the Windows Registry

Another convenient mechanism for use with C++ applications under Windows is to use the system registry¹. Properties can be stored in the registry under the following registry keys:

```
HKEY_LOCAL_MACHINE\Software\OOC\Properties
HKEY_CURRENT_USER\Software\OOC\Properties
```

Individual properties are defined as sub-keys of the base. For example, the property `ooc.orb.trace.connections=5` is stored in the registry as the following key containing a value named `connections` with a REG_SZ data member equal to 5:

```
Software\OOC\Properties\ooc\orb\trace
```

RegUpdate

The Orbacus distribution includes a utility called `RegUpdate`. The tool first removes all sub-keys defined under the specified registry key. Next, all values defined in an Orbacus configuration file are transferred to the registry.

Synopsis

```
RegUpdate HKEY_LOCAL_MACHINE|HKEY_CURRENT_USER config-file
```

Example:

```
RegUpdate HKEY_LOCAL_MACHINE ob.conf
```

This command reads the properties defined in the file `ob.conf` and writes the values under the following registry key:

```
HKEY_LOCAL_MACHINE\Software\OOC\Properties
```

1. Use caution when defining Orbacus properties in the registry, as they become global properties that will be used in every Orbacus for C++ application. For example, subtle errors can occur if the `ooc.iiop.port` property is defined on a global basis.

Defining Properties

Properties in Java

Java applications can use the standard Java mechanism for defining system properties because Orbacus will also search the system properties during ORB initialization.

For example:

```
1 // Java
2 java.util.Properties props = System.getProperties();
3 props.put("ooc.orb.oe.conc_model", "thread_pool");
4 props.put("ooc.orb.oe.thread_pool", "20");
5 org.omg.CORBA.ORB orb = org.omg.CORBA.ORB.init(args, null);
```

Line 2 Obtain the system properties.

Lines 3-4 Define Orbacus properties.

Line 5 Initialize the ORB.

Java virtual machines typically allow you to define system properties on the command line. For example, using Sun's JVM you can do the following:

```
java -Dooc.orb.oe.thread_pool=20 MyServer
```

You can also use the `java.util.Properties` object that is passed to the `ORB.init()` method to provide Orbacus property definitions:

```
1 // Java
2 java.util.Properties props = new java.util.Properties();
3 props.put("ooc.orb.oe.conc_model", "thread_pool");
4 props.put("ooc.orb.oe.thread_pool", "20");
5 org.omg.CORBA.ORB orb = orb.omg.CORBA.ORB.init(args, props);
```

Line 2 Create a `java.util.Properties` object to hold our properties.

Lines 3-4 Define Orbacus properties.

Line 5 Initialize the ORB using the `java.util.Properties` object.

Properties in C++

In C++, the Orbacus-specific class `OB::Properties` can be used to define properties:

```
// C++
class Properties
{
    // ...
public:
    Properties();
    Properties(Properties_ptr p);
    ~Properties();

    static Properties_ptr _duplicate(Properties_ptr p);
    static Properties_ptr _nil();

    static Properties_ptr getDefaultProperties();

    void setProperty(const char* key, const char* value);
    const char* getProperty(const char* key) const;
    // ...
};
```

For example, to add the threaded concurrency model to a property set that is used to initialize the ORB:

```
1 // C++
2 OB::Properties_var dflt =
    OB::Properties::getDefaultProperties();
3 OB::Properties_var props = new OB::Properties(dflt);
4 props -> setProperty("ooc.orb.conc_model", "threaded");
5 CORBA::ORB_var orb = OBCORBA::ORB_init(argc, argv, props);
```

Lines 2-3 Create an `OB::Properties` object that is based on the default properties. This is important because, unlike `org.omg.CORBA.ORB.init`, `OBCORBA::ORB_init` does not read the default properties if the property parameter is not null.

Line 4 Define Orbacus property.

Line 5 Initialize the ORB using the Orbacus-specific `OBCORBA::ORB_init` operation.

Precedence of Properties

Given that properties can be defined in several ways, it's important to establish the order of precedence used by Orbacus when collecting and processing the property definitions. The order of precedence is listed below, from highest to lowest. Properties defined at a higher precedence override the same properties defined at a lower precedence.

1. Command-line options
2. Configuration file specified at the command-line
3. User-supplied properties
4. Configuration file specified by the `ORBACUS_CONFIG` environment variable (C++) or the `ooc.config` system property (Java)
5. System properties (Java only)
6. `HKEY_CURRENT_USER\Software\OOC\Properties` (Windows/C++ only)
7. `HKEY_LOCAL_MACHINE\Software\OOC\Properties` (Windows/C++ only)

For example, a property defined using a command-line option overrides the same property defined in a configuration file.

Advanced Property Usage

With the methods for ORB initialization discussed in the previous sections, the command-line arguments are not processed until a call to `CORBA::ORB_init (C++)`, `OBCORBA::ORB_init (C++)`, or `org.omg.CORBA.ORB.init (Java)`. Hence, the set of properties that will be used by the ORB is not available until after the ORB is initialized. This poses a problem if the properties need to be validated prior to ORB initialization. If you need access to an ORB's property set before it is initialized, then you may elect to use the Orbacus-specific operations `OB::ParseArgs (C++)` or `com.omg.CORBA.ORB.ParseArgs (Java)`.

Examples

The following examples check the value of the `ooc.orb.conc_model` property to ensure that it is set to `threaded`. If not, the code chooses the `threaded` concurrency model.

```

1 // C++
2 #include <OB/Logger.h>
3 #include <OB/Properties.h>
4 ...
5 OB::Properties_var dflt =
    OB::Properties::getDefaultProperties();
6 OB::Properties_var props = new OB::Properties(dflt);
7 OB::ParseArgs(argc, argv, props, OB::Logger::_nil());
8 const char* orbModel = props ->
    getProperty("ooc.orb.conc_model");
9 if(strcmp(orbModel, "threaded") != 0)
10 {
11     props -> setProperty("ooc.orb.conc_model", "threaded");
12 }
13 CORBA::ORB_var orb = OBCORBA::ORB_init(argc, argv, props);

```

Lines 5-6 Create an `OB::Properties` object that is based on the default properties.

Line 7 Initialize the properties for the ORB. After invoking `OB::ParseArgs`, `props` contains the ORB properties and `argv` no longer contains any `-ORB` or `-OA` command-line arguments. The `OB::ParseArgs` operation takes an

optional `Logger` object, which `ParseArgs` will use to display any warning or error messages. In this example, a custom `Logger` object is not used, so the code passes a `nil` value.

Lines 8-12 Retrieve the `ooc.orb.conc_model` property and set it to `threaded` if its value is not valid.

Line 13 Initialize the ORB.

```
1 // Java
2 java.util.Properties props = System.getProperties();
3 args = com.ooc.CORBA.ORB.ParseArgs(args, props, null);
4 String orbModel = props.get("ooc.orb.conc_model");
5 if(!orbModel.equals("threaded"))
6 {
7     props.put("ooc.orb.conc_model", "threaded");
8 }
9 org.omg.CORBA.ORB orb = org.omg.CORBA.ORB.init(arg, props);
```

Line 2 Create a `java.util.Properties` object.

Line 3 Initialize the properties for the ORB. After invoking `com.ooc.CORBA.ORB.ParseArgs`, `props` contains the ORB properties. The return value of `ParseArgs` is a string array with all `-ORB` and `-OA` arguments removed. As in the C++ example, a `Logger` object is not used.

Lines 4-8 Retrieve the `ooc.orb.conc_model` property and set it to `threaded` if its value is not valid.

Line 9 Initialize the ORB.

Using POA Managers

The CORBA specification states that a POA Manager is used to control the flow of requests to one or more POAs. In Orbacus, each POA Manager also encapsulates a set of network endpoints on which a server listens for new connections. This design provides applications with a great deal of flexibility:

- endpoints can be activated and deactivated on demand
- a group of endpoints can be controlled using a single POA Manager and serviced by one or more POAs

In this section

This section contains the following sections:

The Root POA Manager	page 98
Anonymous POA Managers	page 99
The POA Manager Factory	page 100
Creating a POA Manager	page 101
POA Manager Policies	page 103
Endpoints	page 104
Command-line Options and Endpoints	page 105
Dispatching Requests	page 106
Callbacks	page 107

The Root POA Manager

As its name suggests, the Root POA Manager is the POA Manager of the Root POA. When the Root POA is first resolved using `resolve_initial_references`, the Root POA Manager is automatically created to manage the Root POA. For administrative purposes, the name of the Root POA Manager is `RootPOAManager`.

Anonymous POA Managers

An application can implicitly create POA Managers by supplying a `nil` value for the POA Manager argument to the `create_POA` operation. In fact, this is the only portable means of creating POA Managers.¹ In this text, we'll refer to POA Managers created in this way as anonymous POA Managers.

One limitation of anonymous POA Managers in Orbacus is that their endpoints cannot be configured externally via properties, therefore anonymous POA Managers always use the default endpoint configuration. Specifically, each anonymous POA Manager will create a single IIOP endpoint on a port chosen by the operating system. Consequently, object references created by POAs managed by an anonymous POA Manager are inherently transient.²

Applications which require configurable POA Managers (in addition to the Root POA Manager) can use the proprietary POA Manager factory, described in the next section.

1. IONA has proposed adding support for POA Manager identity. For details, see http://cgi.omg.org/issues/orb_revision.html#Issue4297.
2. Unless of course an indirect persistence mechanism such as the Implementation Repository is in use.

The POA Manager Factory

To allow an application to easily configure POA Managers, Orbacus provides the standard CORBA 3.0 factory interface for creating named POA Managers:

```
// IDL
module PortableServer
{
    local interface POAManagerFactory
    {
        typedef sequence< POAManager > POAManagerSeq;

        exception ManagerAlreadyExists
        {
        };

        POAManager create_POAManager(in string id,
                                     in CORBA::PolicyList policies)
            raises (ManagerAlreadyExists,
                  CORBA::PolicyError);

        POAManagerSeq list();

        POAManager find(in string id);
    };

    ...

    local interface POA
    {
        ...

        readonly attribute POAManagerFactory the_POAManagerFactory;

        ...
    };

    ...
};
```

Creating a POA Manager

The example below illustrates how to create a new POA Manager using the POA Manager Factory. For this example, an empty policy list is used.

Here is an example in C++:

```
1 // C++
2 CORBA::Object_var poaObj =
3     orb -> resolve_initial_references("RootPOA");
4 OBPortableServer::POA_var rootPOA =
5     OBPortableServer::POA::_narrow(poaObj);
6 POAManagerFactory_var factory = rootPOA ->
7     the_POAManagerFactory();
8 OBPortableServer::POAManagerFactory_var pmFactory =
9     OBPortableServer::POAManagerFactory::_narrow(factory);
10 POAManager_var myPOAManager;
11 PolicyList pl;
12 try
13 {
14     myPOAManager = pmFactory ->
15         create_POAManager("MyPOAManager", pl);
16 }
17 catch(const POAManagerFactory::ManagerAlreadyExists& ex)
18 {
19     // do something
20 }
```

Lines 2-6 Resolve the POA Manager Factory.

Lines 7-16 Create a new POA Manager with the name MyPOAManager.

And in Java:

```

1 // Java
2 org.omg.CORBA.Object obj =
3   orb.resolve_initial_references("RootPOA");
4 org.omg.PortableServer.POA rootPOA =
5   org.omg.PortableServer.POAHelper.narrow(obj)
6 org.omg.PortableServer.POAManagerFactory factory =
7   rootPOA.the_POAManagerFactory();
8 com.ooc.OBPortableServer.POAManagerFactory pmFactory =
9
10  com.ooc.OBPortableServer.POAManagerFactoryHelper.narrow(factory);
11 org.omg.PortableServer.POAManager myPOAManager = null;
12 org.omg.CORBA.Policy[] pl = new Policy[0];
13 try
14 {
15     myPOAManager =
16     pmFactory.create_POAManager("MyPOAManager", pl);
17 }
18 catch(org.omg.PortableServer.POAManagerFactoryPackage.Manager
19 AlreadyExists ex)
20 {
21     // do something
22 }
23 catch(org.omg.CORBA.PolicyError ex)
24 {
25     // do something
26 }

```

Lines 2-9 Resolve the POA Manager Factory.

Lines 10-17 Create a new POA Manager with the name MyPOAManager. The ORB processes any configuration properties that were defined for the POA Manager, and may raise the `OCI::InvalidParam` exception if an error was found in the POA Manager's endpoint configuration.

POA Manager Policies

The POA Manager Factory interface allows a set of vendor-specific policies to be used to configure the new POA Manager. For Orbacus, the proprietary policies are:

```
// IDL
module OBPortableServer
{
    local interface POAManagerFactory :
    PortableServer::POAManagerFactory
    {
        EndpointConfigurationPolicy
        create_endpoint_configuration_policy(
            in string value)
            raises (CORBA::PolicyError);

        CommunicationsConcurrencyPolicy
        create_communications_concurrency_policy(
            in short value)
            raises (CORBA::PolicyError);

        GIOFVersionPolicy create_giop_version_policy(
            in short value)
            raises (CORBA::PolicyError);
    };
    ...
};
```

These policies map to the POA Manager specific configuration properties (`ooc.orb.poamanager.manager.`) `endpoint`, `conc_model`, and `version` (see [“OA Properties” on page 85](#)). For examples of how to use these policies, refer to [“Using Policies” on page 329](#).

Endpoints

Orbacus supports a flexible mechanism for configuring a POA Manager's endpoints via properties. A single property is used to configure the endpoints for a particular POA Manager. The property value consists of a comma-separated list of endpoints, with the following syntax:

plugin-id [options] [, plugin-id [options] ...]

For example:

```
ooc.orb.oa.endpoint=iiop --port 9998, iiop --port 9999
ooc.orb.poamanager.MyManager.endpoint=iiop
```

This configuration creates two IIOp endpoints for the Root POA Manager on specific ports, and one IIOp endpoint for the POA Manager named 'MyManager' on an arbitrary port. Technically, the second property isn't necessary, because this is the default configuration if no endpoints are specified for a POA Manager.

It is important to note that only those transport plug-ins which were installed via the `ooc.oci.server` property can be used in endpoint configuration.

When experimenting with various endpoint configurations, it can be very useful to enable connection tracing diagnostics. With diagnostics enabled, the ORB will display its endpoint information, allowing you to confirm that the application's endpoints are configured correctly. Diagnostics can be enabled using the `-ORBtrace_connections` command-line option, or using the equivalent property `ooc.orb.trace.connections`.

See [“Configuring the ORB and Object Adapter” on page 77](#) for more information on configuration properties.

For a complete description of the available transport plug-ins and their options, see [Chapter 19](#).

Command-line Options and Endpoints

Transport plug-ins may support command-line options, and it is important to understand the effects of using those options. They can be summarized as follows:

- Using a plug-in's command-line options will always *add* a new endpoint configuration. That is, command-line options do not override an existing endpoint configuration.
- Command-line options only configure endpoints for the Root POA Manager.

The first item is the most significant. Let's consider some examples which will serve to explain this issue. First, assume that there is no endpoint configuration property for the Root POA Manager, and that we use the following command-line options:

```
-IIOPhost host.abc.com -IIOPport 1234
```

The IIOp plug-in will convert these command-line options into the following configuration property:

```
ooc.orb.oa.endpoint=iiop --host host.abc.com --port 1234
```

Now let's consider a more complicated example. Suppose that we have an existing endpoint configuration property defined, and we also use command-line options. The existing endpoint configuration is

```
ooc.orb.oa.endpoint=iiop --port 5555
```

And the command-line options are

```
-IIOPport 5556
```

After the command-line options are processed by the IIOp plug-in, the endpoint configuration property will be

```
ooc.orb.oa.endpoint=iiop --port 5555, iiop --port 5556
```

Note that there are now two endpoints; the command-line options resulted in an additional endpoint being appended to the existing property value.

Dispatching Requests

As explained in [4], a POA Manager is initially in the holding state, where incoming requests on the POA Manager's endpoints are queued. To dispatch requests, the POA Manager must be activated using the `activate()` operation.

Callbacks

In mixed client/server applications in which callbacks occur, it is important to remember that callbacks will not be dispatched until the POA Manager has been activated. If the POA Manager has not been activated, the application will likely hang. In general, applications should activate the POA Manager prior to making any request that might result in a callback.

ORB Destruction

Applications must destroy the ORB before returning from `main` so that resources used by the ORB are properly released.

To destroy the ORB in C++, invoke `destroy` on the ORB:

```
// C++
CORBA::ORB_var orb = // Initialize the orb
// ...
orb -> destroy();
```

And in Java:

```
// Java
org.omg.CORBA.ORB orb = // Initialize the orb
// ...
orb.destroy();
```

Server Event Loop

A server's event loop is entered by calling `POAManager::activate` on each POA Manager, and then calling `ORB::run`.

For example, in Java:

```
// Java
org.omg.CORBA.ORB orb = ... // Initialize the orb
org.omg.PortableServer.POAManager manager = ... // Get Root POA
manager
manager.activate();
orb.run();
```

And in C++:

```
// C++
CORBA::ORB_var orb = ... // Initialize the orb
PortableServer::POAManager_var manager = ... // Get the Root POA
manager
manager -> activate();
orb -> run();
```

You can deactivate a server by calling `ORB::shutdown`, which causes `ORB::run` to return. For example, consider a server that can be shut down by a client by calling a `deactivate` operation on one of the server's objects.

First the IDL code:

```
// IDL
interface ShutdownObject
{
    void deactivate();
};
```

On the server side, `ShutdownObject` can be implemented like this:

```

1 // C++
2 class ShutdownObject_impl :
3     public POA_ShutdownObject,
4     public PortableServer::RefCountServantBase
5 {
6     CORBA::ORB_var orb_;
7
8 public:
9
10    ShutdownObject_impl(CORBA::ORB_ptr orb)
11        : orb_(CORBA::ORB::_duplicate(orb))
12    {
13    }
14
15    virtual void deactivate() throw(CORBA::SystemException)
16    {
17        orb_ -> shutdown(false);
18    }
19 }

```

Lines 2-3 A servant class for `ShutdownObject` is defined. For more information on how to implement servant classes, see [Chapter 5](#).

Line 5 An ORB is needed to call `shutdown`.

Lines 9-12 The constructor initializes the ORB member.

Lines 14-17 `deactivate` calls `shutdown` on the ORB. Note that `shutdown` is called with the argument `false` to avoid a deadlock. A `false` argument instructs `shutdown` to terminate request processing without waiting for executing operations to complete. A `true` argument instructs `shutdown` to return only once all operations have completed. If `shutdown` were called with a `true` argument in this example, it would deadlock. That is because `shutdown(true)` would be invoked from within an operation and, therefore, could not ever return.

The client can use the `deactivate` call as shown below:

```

// C++
ShutdownObject_var shutdownObj = ... // Get a reference somehow
shutdownObj -> deactivate();

```

CORBA Objects

This chapter describes how to create and use CORBA servant objects.

In this chapter

This chapter contains the following sections:

Overview	page 112
Implementing Servants	page 114
Creating Servants	page 123
Activating Servants	page 128
Deactivating Servants	page 133
Factory Objects	page 135

Overview


A *CORBA object* is an object with an interface defined in CORBA IDL. CORBA objects have different representations in clients and servers.

- A *server* implements a CORBA object in a concrete programming language, for example in C++ or Java. This is done by writing an *implementation class* for the CORBA object and by instantiating this class. The resulting implementation object is called a *servant*.
- A *client* that wants to make use of an object implemented by a server creates an object that delegates all operation calls to the servant via the ORB. Such an object is called a *proxy*.

When a client invokes a method on the local proxy object, the ORB packs the input parameters and sends them to the server, which in turn unpacks these parameters and invokes the actual method on the servant. Output parameters and return values, if any, follow the reverse path back to the client. From the client's perspective, the proxy acts just like the remote object since it hides all the communication details within itself.

A servant must somehow be connected to the ORB, so that the ORB can invoke a method on the servant when a request is received from a client. This connection is handled by the *Portable Object Adapter (POA)*, as shown in [Figure 2](#).

Figure 2: *Servants, Proxies and the Object Adapter*



The Portable Object Adapter in Orbacus replaces the deprecated Basic Object Adapter (BOA). (The BOA was deprecated by the OMG because it had a number of serious deficiencies and was under-specified.) The POA is

a far more flexible and powerful object adapter than the BOA. The POA not only allows you to write code that is portable among ORBs from different vendors, it also provides a number of features that are essential for building high-performance and scalable servers.

Implementing Servants

In this section, we will implement servant classes (or implementation classes) for the IDL interfaces defined below:

```
1 // IDL
2 interface A
3 {
4     void op_a();
5 };
6
7 interface B
8 {
9     void op_b();
10 };
11
12 interface I : A, B
13 {
14     void op_i();
15 };
```

Lines 2-5 An interface `A` is defined with the operation `op_a`.

Lines 7-10 An interface `B` is defined with the operation `op_b`.

Lines 12-15 Interface `I` is defined, which is derived from `A` and `B`. It also defines a new operation `op_i`.

Implementing Servants using Inheritance

Overview

Orbacus for C++ and Orbacus for Java both support the use of inheritance for interface implementation. To implement an interface using inheritance, you write a servant class that inherits from a skeleton class generated by the IDL translator. By convention, the name of the servant class should be the name of the interface with the suffix `_impl`. For example, for an interface `I`, the implementation class is named `I_impl`.¹

Inheritance using C++

In C++, `I_impl` must inherit from the skeleton class `POA_I` that was generated by the IDL-to-C++ translator. If `I` inherits from other interfaces, for example from the interfaces `A` and `B`, then `I_impl` must also inherit from the corresponding implementation classes `A_impl` and `B_impl`.

```

1 // C++
2 class A_impl : virtual public POA_A
3 {
4 public:
5     virtual void op_a() throw(CORBA::SystemException);
6 };
7
8 class B_impl : virtual public POA_B
9 {
10 public:
11     virtual void op_b() throw(CORBA::SystemException);
12 };
13
14 class I_impl : virtual public POA_I,
15                virtual public A_impl,
16                virtual public B_impl
17 {
18 public:
19     virtual void op_i() throw(CORBA::SystemException);
20 };

```

Lines 2-6 The servant class `A_impl` is defined, inheriting from the skeleton class `POA_A`. If `op_a` had any parameters, these parameters would be mapped according to the standard IDL-to-C++ mapping rules [4].

Lines 8-13 This is the servant class for `B_impl`.

1. These naming rules are a recommendation, and are not mandatory.

Lines 14-20 The servant class for `I_impl` is not only derived from `POA_I`, but also from the servant classes `A_impl` and `B_impl`.

Note that `virtual public` inheritance must be used. The only situation in which the keyword `virtual` is not necessary is for an interface `I` which does not inherit from any other interface and from which no other interface inherits. This means that the implementation class `I_impl` only inherits from the skeleton class `POA_I` and no implementation class inherits from `I_impl`.

It is not strictly necessary to have an implementation class for every interface. For example, it is sufficient to only have the class `I_impl` as long as `I_impl` implements all interface operations, including the operations of the base interfaces:

```
1 // C++
2 class I_impl : virtual public POA_I
3 {
4 public:
5     virtual void op_a() throw(CORBA::SystemException);
6     virtual void op_b() throw(CORBA::SystemException);
7     virtual void op_i() throw(CORBA::SystemException);
8 };
```

Line 2 Now `I_impl` is only derived from `POA_I`, but not from the other servant classes.

Lines 5-7 `I_impl` must implement all operations from the interface `I` as well as the operations of all interfaces from which `I` is derived.

Inheritance using Java

Several files are generated by the Orbacus IDL-to-Java translator for an interface `I`, including:

- `I.java`, which defines a Java interface `I` containing public methods for the operations and attributes of `I`, and
- `IPOA.java`, which is an abstract skeleton class that serves as the base class for servant classes.

In contrast to C++, Java's lack of multiple inheritance currently makes it impossible for a servant class to inherit operation implementations from other servant classes, except when using delegation-based implementation.

For our interface `I` it is therefore necessary to implement all operations in a single servant class `I_impl`, regardless of whether those operations are defined in `I` or in an interface from which `I` is derived.

```
// Java
public class I_impl extends IPOA
{
    public void op_a()
    {
    }

    public void op_b()
    {
    }

    public void op_i()
    {
    }
}
```

The servant class `I_impl` is defined, which implements `op_i`, as well as the inherited operations `op_a` and `op_b`.

Implementing Servants using Delegation

Sometimes it is not desirable to use an inheritance-based approach for implementing an interface. This is especially true if the use of inheritance would result in overly complex inheritance hierarchies (for example, because of use of an existing class library that requires extensive use of inheritance). Therefore, another alternative is available for implementing servants which does not use inheritance. A special class, known as a *tie class*, can be used to delegate the implementation of an interface to another class.¹

Delegation using C++


The Orbacus IDL-to-C++ translator can automatically generate a tie class for an interface in the form of a template class. A tie template class is derived from the corresponding skeleton class and has the same name as the skeleton, with the suffix `_tie` appended.

For the interface `I` from the C++ example above, the template `POA_I_tie` is generated and must be instantiated with a class that implements all operations of `I`. By convention, the name of this class should be the name of the interface with `_impl_tie` appended.²

1. Note that tie classes are rarely necessary. Not only is the inheritance implementation less complex, but it also avoids a number of problems that arise with the life cycle of objects, particularly in threaded servers. We suggest that you use the tie approach only if you have no other option.
2. Again, you are free to choose whatever name you like. This is just a recommendation.

In contrast to the inheritance-based approach, it is not necessary for the class implementing `I`'s operations, `I_impl_tie`, to be derived from a skeleton class. Instead, an instance of `POA_I_tie` delegates all operation calls to `I_impl_tie`, as shown in [Figure 3](#).

Figure 3: *Class Hierarchy for Delegation Implementation in C++*



Here is our definition of `I_impl_tie`:

```

// C++
class I_impl_tie
{
public:
virtual void op_a() throw(CORBA::SystemException);
virtual void op_b() throw(CORBA::SystemException);
virtual void op_i() throw(CORBA::SystemException);
};
  
```

Line 2 `I_impl_tie` is defined and not derived from any other class.

Lines 5-7 `I_impl_tie` must implement all of `I`'s operations, including inherited operations.

A servant class for `I` can then be defined using the `I_skel_tie` template:

```

// C++
typedef POA_I_tie< I_impl_tie > I_impl;
  
```

The servant class `I_impl` is defined as a template instance of `POA_I_tie`, parameterized with `I_impl_tie`.

The tie template generated by the IDL compiler contains functions that permit you change the instance denoted by the tie:

```

1 // C++
2 template<class T>
3 class POA_I_tie : public POA_I
4 {
5 public:
6     // ...
7     T* _tied_object();
8     void _tied_object(T& obj);
9     void _tied_object(T* obj, CORBA::Boolean release = true);
10    // ...
11 }

```

Lines 7-9 The `_tied_object` function permits you to retrieve and change the implementation instance that is currently associated with the tie. The first modifier function calls `delete` on the current tied instance before accepting the new tied instance if the `release` flag is currently true; the `release` flag for the new tied instance is set to false. The second modifier function also calls `delete` on the current tied instance before accepting the new instance but sets the `release` flag to the passed value.

Delegation using Java

For every IDL interface, the IDL-to-Java mapping generates an operations interface containing methods for the IDL attributes and operations. This operations interface is also used to support delegation-based servant implementation. For an interface `I`, the following additional class is generated:

- `IPOATie.java`, the tie class that inherits from `IPOA` and delegates all requests to an instance of `IOperations`.

To implement our servant class using delegation, we need to write a class that implements the `IOperations` interface:

```

1 // Java
2 public class I_impl_tie implements IOperations
3 {
4     public void op_a()
5     {
6     }
7
8     public void op_b()
9     {
10    }
11
12    public void op_i()
13    {
14    }
15 }


```

Line 2 The servant class `I_impl_tie` is defined to implement the `IOperations` interface.

Lines 4-14 `I_impl_tie` must implement all of `I`'s operations, including inherited operations.

[Figure 4](#) illustrates the relationship between the classes generated by the IDL-to-Java translator and the servant implementation classes.

Figure 4: *Class Hierarchy for Inheritance and Delegation Implementation in Java*



As noted earlier, Java's lack of multiple inheritance makes it impossible to inherit an implementation from another servant class. Using tie classes, however, does allow implementation inheritance, but only in certain situations.

For example, let's implement each of our sample interfaces using delegation.

```
1 // Java
2 public class A_impl implements AOperations
3 {
4     public void op_a()
5     {
6     }
7 }
8
9 public class B_impl implements BOperations
10 {
11     public void op_b()
12     {
13     }
14 }
15
16 public class I_impl extends B_impl implements IOperations
17 {
18     public void op_a()
19     {
20     }
21
22     public void op_i()
23     {
24     }
25 }
```

Lines 2-7 Class `A_impl` is defined as implementing `AOperations`.

Lines 9-14 Class `B_impl` is defined as implementing `BOperations`.

Lines 16-21 Class `I_impl` inherits the implementation of `op_b` from `B_impl`, and provides an implementation of `op_a` and `op_i`. Since a Java class can only extend one class, it's not possible for `I_impl` to inherit the implementations of both `op_a` and `op_b`.

Creating Servants

Servants are created the same way in both C++ and Java: once your servant class is written, you simply instantiate a servant with `new`.¹

1. You can also instantiate servants on the stack. However, this only works only for some POA policies, so servants are usually instantiated on the heap.

Creating Servants using C++

Here is how to create servants using C++:

```
// C++
I_impl* servant_pointer = new I_impl;
I_impl* another_servant_pointer = new I_impl;
```

Two servants are created with `new`. Note that this merely instantiates the servants but does not inform the ORB that these servants exist yet. The ORB server-side run time only learns of the existence of the servants once you activate them.

In case the servant class was written using the delegation approach, an object of the class implementing `I`'s operations must be passed to the servant's constructor:

```
1 // C++
2 I_impl_tie* impl = new I_impl_tie;
3 POA_I_tie< I_impl_tie >* tie_pointer =
4   new POA_I_tie< I_impl_tie >(impl);
```

Line 2 A new `I_impl_tie` is created with `new`.

Lines 3-4 An instance of `POA_I_tie` parameterized with `I_impl_tie` is created, taking `impl` as a parameter. All operation calls to `tie` will then be delegated to `impl`.

In this example, the lifetime of `impl` is coupled to the lifetime of the servant tie. That is, when the tie is destroyed, `delete impl` is called by the tie's destructor. In case you don't want the lifetime of `impl` to be coupled to the lifetime of the tie, for example, because you want to create a servant on the stack and not on the heap (making it illegal to call `delete` on the tie), use the following code:

```
1 // C++
2 I_impl_tie impl;
3 POA_I_tie< I_impl_tie >* tie =
4   new POA_I_tie< I_impl_tie >(&impl, false);
```

Line 2 A new `I_impl_tie` is created, this time on the stack, not on the heap.

Lines 3-4 An instance of `POA_I_tie` is created. The `false` parameter tells `tie` not to call `delete` on `impl`.

Creating Servants using Java

Every tie class generated by the IDL-to-Java translator has two constructors:

```
// Java
public class IPOATie extends IPOA
{
    public IPOATie(IOperations delegate) { ... }
    public IPOATie(IOperations delegate, POA poa) { ... }
    ...
}
```

The second constructor allows a POA instance to be supplied, which will be used as the return value for the tie's `_default_POA` method. If the POA instance is not supplied, the `_default_POA` method will return the root POA of the ORB with which the tie has been associated.

This example demonstrates how to create servants using Java:

```
// Java
I_impl impl = new I_impl();
I_impl anotherImpl = new I_impl();
```

Two servants, `impl` and `anotherImpl`, are created with `new`.

In case the servant class was written using the delegation approach, an object implementing the `IOperations` interface must be passed to the tie's constructor:

```
1 // Java
2 I_impl_tie impl = new I_impl_tie();
3 IPOATie tie = new IPOATie(impl);
```

Line 2 A new `I_impl_tie` is created.

Line 3 An instance of `IPOATie` is created, taking `impl` as a parameter. All operation calls to `tie` will then be delegated to `impl`.

The tie class also provides methods for accessing and changing the implementation object:

```
1 // Java
2 public class IPOATie extends IPOA
3 {
4     ...
5     public IOperations _delegate() { ... }
6     public void _delegate(IOperations delegate) { ... }
7     ...
8 }
```

Line 5 This method returns the current delegate (that is, implementation) object.

Line 6 This method changes the delegate object.

Activating Servants

Servants must be activated in order to receive requests from clients. Servant activation informs the ORB run time which particular servant represents (or *incarnates*) a particular CORBA object. Activation of a servant assigns an *object identifier* to the servant. That object identifier is also embedded in every object reference that is created for an object and serves to link the object reference with its servant.

The POA's `IdAssignmentPolicy` value controls whether object IDs are assigned by the POA or the server application code. The `SYSTEM_ID` policy value directs the ORB to assign a unique object identifier to the CORBA object represented by the servant; the `USER_ID` policy value requires the server application code to supply an ID that must be unique within the servant's POA.

Servants can be activated implicitly or explicitly. Implicit activation takes place when you create the first object reference for a servant. Explicit activation requires a separate API call. Typically, you will use implicit activation for transient objects and explicit activation for persistent objects. The `ImplicitActivationPolicy` controls whether explicit or implicit is in effect. Explicit activation requires the `NO_IMPLICIT_ACTIVATION` policy value on the servant's POA, whereas implicit activation requires the `IMPLICIT_ACTIVATION` policy value.

Implicit Activation of Servants using C++

The following code shows how to implicitly activate a servant:

```
1 // C++
2 I_impl impl;
3 I_var iv = impl -> _this();
```

Line 2 A new servant `impl` is created.

Line 3 The new servant is activated implicitly by calling `_this`.

Note that implicit activation as shown requires the `RETAIN`, `IMPLICIT_ACTIVATION`, and `SYSTEM_ID` policies on the servant's POA. The servant is activated with the POA that is returned by the servant's `_default_POA` member function. (The default implementation of `_default_POA` returns the Root POA; if you want servants activated on a different POA, you must override `_default_POA` in the implementation class to return the POA you want to use.)

Implicit Activation of Servants using Java

This is how Java servants are implicitly activated:

```
1 // Java
2 org.omg.CORBA.ORB orb = ... // Get a reference to the ORB
   somehow
3 I_impl impl = new I_impl();
4 I Iref = impl._this(orb);
```

Line 2 To activate a servant, we need the ORB.

Line 3 A new servant `impl` is created.

Line 4 The new servant is activated (using the POA returned by the servant's `_default_POA` operation).

As shown above, a servant in Java must be associated with an ORB, and cannot be associated with multiple ORBs. The first call to `_this()` must supply the ORB reference; subsequent calls to `_this()` for the same servant can omit the ORB reference.

An alternative way to associate a servant with an ORB is to call the `set_delegate` method defined in `org.omg.CORBA_2_3.ORB`.

```
// Java
org.omg.CORBA.ORB orb = ... // Get a reference to the ORB somehow
((org.omg.CORBA_2_3.ORB)orb).set_delegate(impl);
```

Explicit Activation of Servants using C++

If `NO_IMPLICIT_ACTIVATION` and `SYSTEM_ID` are in effect for a servant's POA, you activate the servant by calling `activate_object`:

```
1 I_impl impl;
2 PortableServer::POA_var poa = impl._default_POA();
3 poa -> activate_object(&impl);
```

Line 1 The code instantiates a servant.

Line 2 To activate a servant, we need the servant's POA.

Line 3 `activate_object` creates a unique ID for the servant.

Once a servant is activated, calls to `_this` on the servant return an object reference that contains the ORB-assigned ID for the object.

If `NO_IMPLICIT_ACTIVATION` and `USER_ID` are in effect for servant's POA, you activate the servant by supplying the ID value as an octet sequence to `activate_object_with_id`:

```
1 I_impl impl;
2 PortableServer::POA_var poa = impl._default_POA();
3 PortableServer::ObjectId_var oid =
4     PortableServer::string_to_ObjectId("MyObjectName");
5 poa -> activate_object_with_id(oid, &impl);
```

Lines 3-4 The `string_to_ObjectId` helper function converts a string into an octet sequence.

Line 5 `activate_object_with_id` uses the octet sequence as the object ID for the servant.

You can use any suitable key value as an object ID. Typically, the key will be part of the object's state, such as a social security number. However, you can also use keys that are not directly related to object state, such as database record identifiers. Once the servant is activated, calls to `_this` on the servant return an object reference that contains the ID you assigned to the object.

Explicit Activation of Servants using Java

Servant activation in Java also uses `activate_object` (for `SYSTEM_ID`) and `activate_object_with_id` (for `USER_ID`). With `SYSTEM_ID`, the code looks as follows:

```
I_impl impl = new I_impl();
orb.omg.PortableServer.POA poa = impl._default_POA();
poa.activate_object(impl);
```

For `USER_ID`, you must provide the Object ID:

```
I_impl impl = new I_impl();
org.omg.PortableServer.POA poa = impl._default_POA();
byte[] id = "MyObjectName".getBytes();
poa.activate_object_with_id(id, impl);
```

Deactivating Servants

Deactivation of Servants using C++

A servant can be deactivated. Deactivating a servant breaks the association between the CORBA object and the servant; requests that arrive from clients thereafter result in an `OBJECT_NOT_EXIST` exception (or a `TRANSIENT` exception, if the server is down at the time a request is made).

To deactivate a servant, call the `deactivate_object` member function on the servant's POA:

```
1 // C++
2 PortableServer::POA_var poa = impl._default_POA();
3 PortableServer::ObjectId_var id = poa -> servant_to_id(&impl);
4 poa -> deactivate_object(id);
```

Line 2 The code obtains a reference to the servant's POA by calling `_default_POA`. (This assumes that `_default_POA` is correctly overridden to return the appropriate POA if the servant is not activated with the Root POA.)

Line 3 The call to `servant_to_id` on the servant's POA returns the object ID with which the servant is activated.

Line 4 The call to `deactivate_object` breaks the association between the CORBA object and the servant.

Note that `deactivate_object` returns immediately, even though the servant may still be executing requests, possibly in a number of different threads.

Deactivation of Servants using Java

Deactivation of a servant in Java is analogous to C++:

```
// Java
org.omg.PortableServer.POA poa = impl._default_POA();
byte[] id = poa.servant_to_id(impl);
poa.deactivate_object(id);
```

Transient and Persistent Objects

A POA has either the `TRANSIENT` or the `PERSISTENT` policy value. A transient POA generates transient object references. A transient object reference remains functional only for as long as its POA remains in existence. Once the POA for a transient reference is destroyed, the reference becomes permanently non-functional and client requests on such a reference raise either `OBJECT_NOT_EXIST` or `TRANSIENT` (depending on whether or not the server is running at the time the request is sent). Transient references remain non-functional even if you restart the server and re-create a transient POA with the same name as was used previously. Transient POAs almost always use the `SYSTEM_ID` policy as a matter of convenience (although the combination of `TRANSIENT` and `USER_ID` is legal).

Object references created on a persistent POA continue to be valid beyond the POA's life time. That is, if you create a persistent reference on a POA, destroy the POA, and then recreate that POA again (with the same POA name), the original reference continues to denote the same CORBA object (even if the server was shut down and restarted). Persistent references require the same POA name and object ID to be used to denote the same object. This means that persistent references rely on the combination of `PERSISTENT` and `USER_ID`. `USER_ID` must be used in conjunction with `NO_IMPLICIT_ACTIVATION`, so servants for persistent references are always activated explicitly.

Factory Objects

It is quite common to use the Factory [2] design pattern in CORBA applications. In short, a factory object provides access to one or more additional objects. In CORBA applications, a factory object can represent a focal point for clients. In other words, the object reference of the factory object can be published in a well-known location, and clients know that they only need to obtain this object reference in order to gain access to other objects in the system, thereby minimizing the number of object references that need to be published.

The Factory pattern can be applied in a wide variety of situations, including the following:

- **Security** - A client is required to provide security information before the factory object will allow the client to have access to another object.
- **Load-balancing** - The factory object manages a pool of objects, often representing some limited resource, and assigns them to clients based on some utilization algorithm.
- **Polymorphism** - A factory object enables the use of polymorphism by returning object references to different implementations depending on the criteria specified by a client.

These are only a few examples of the potential applications of the Factory pattern. The examples listed above can also be used in any combination, depending on the requirements of the system being designed. Note that the factory pattern applies equally to persistent and transient objects.

A simple application of the Factory pattern, in which a new object is created for each client, is illustrated below. The implementation uses the following interface definitions:

```
1 // IDL
2 interface Product
3 {
4     void destroy();
5 };
6
7 interface Factory
8 {
9     Product createProduct();
10 };
```

Lines 2-5 The `Product` interface is defined. The `destroy` operation allows a client to destroy the object when it is no longer needed.

Lines 7-10 The `Factory` interface is defined. The `createProduct` operation returns the object reference of a new `Product`.

Factory Objects using C++

First, we'll implement the `Product` interface:

```
1 // C++
2 class Product_impl :
3     public virtual POA_Product,
4     public virtual PortableServer::RefCountServantBase
5 {
6 public:
7
8     virtual void destroy() throw(CORBA::SystemException)
9     {
10         PortableServer::POA_var poa = _default_POA();
11         PortableServer::ObjectId_var id = poa ->
servant_to_id(this);
12         poa -> deactivate_object(id);
13     }
14 };
```

Lines 2-4 The servant class `Product_impl` is defined as an implementation of the `Product` interface. In addition, `Product_impl` inherits from `RefCountServantBase`, which makes the servant reference counted.

Lines 8-13 The `destroy()` operation deactivates the servant with the POA. As a result, the POA will release all references it maintains to the servant. Since there are no other references to the servant left, the servant's reference count will drop to zero, and thus the servant is destroyed.

Next, we'll implement the factory:

```

1 // C++
2 class Factory_impl : public virtual POA_Factory
3 {
4 public:
5
6     virtual Product_ptr
7     createProduct() throw(CORBA::SystemException)
8     {
9         Product_impl* impl = new Product_impl(orb_);
10        PortableServer::ServantBase_var servant = impl;
11        PortableServer::POA_var poa = ... // Get servant's POA
12        PortableServer::ObjectId_var id = ... // Assign an ID
13        poa -> activate_object_with_id(id, impl);
14        return impl -> _this();
15    }
16 };

```

Line 2 The servant class `Factory_impl` is defined as an implementation of the `Factory` interface.

Lines 9-10 A new reference counted `Product` servant is instantiated. The servant is assigned to a `ServantBase_var`, which decrements the servant's reference count when it goes out of scope.

Lines 11-14 Activates the servant and returns an object reference to the client.

It is important to understand how the servant is eventually destroyed. The `RefCountServantBase` class from which the servant inherits implements a reference count. When the servant is instantiated, the `RefCountServantBase` constructor sets this reference count to 1. When the servant is activated with the POA, the POA increases the reference count by at least 1. When the `ServantBase_var` we assigned the servant to goes out of scope, the reference count is decremented by 1. This means that when `createProduct()` returns, only the POA is holding a reference to the servant. Later, when the servant is deactivated in `destroy()`, the POA decrements the reference count by exactly the same number it used to increment the reference count upon activation. This causes the reference count to drop to zero, in which case the servant will be implicitly deleted.

Note that whenever the ORB starts to dispatch a request on the servant, the reference count is incremented. After request dispatching is finished, the count is decremented by the same amount. This ensures that a reference counted servant cannot be deleted while a request is executing.

Factory Objects using Java

Here is our Java implementation of the `Product` interface:

```

1 // Java
2 public class Product_impl extends ProductPOA
3 {
4     public void destroy()
5     {
6         byte[] id = _default_POA().servant_to_id(this);
7         _default_POA().deactivate_object(id);
8     }
9 }

```

Line 2 Servant class `Product_impl` is defined as an implementation of the `Product` interface.

Lines 6-7 The `destroy` operation deactivates the servant with the POA. As long as no other references to the servant are held in the server, the object will be eligible for garbage collection.

Here's our implementation of the factory:

```

1 // Java
2 public class Factory_impl extends FactoryPOA
3 {
4     public Product createProduct()
5     {
6         Product_impl result = new Product_impl(orb_);
7         org.omg.PortableServer.POA poa = ... // Get servant's
        POA
8         byte[] id = ... // Assign an ID
9         poa.activate_object_with_id(id, result);
10        return result._this(orb_);
11    }
12 }

```

Line 2 Servant class `Factory_impl` is defined as an implementation of the `Factory` interface.

Lines 4-11 The `createProduct` operation instantiates a new `Product` servant, activates it with the POA, and returns an object reference to the client.

Caveats

In these simple examples, the factory objects do not maintain any references to the `Product` servants they create; it is the responsibility of the client to ensure that it destroys a `Product` object when it is no longer needed. This design has a significant potential for resource leaks in the server, as it is quite possible that a client will not destroy its `Product` objects, either because the programmer who wrote the client forgot to invoke `destroy`, or because the client program crashed before it had a chance to clean up. You should keep these issues in mind when designing your own factory objects.¹

1. Two possible strategies for handling this issue include: time-outs, in which a servant that has not been used for some length of time is automatically released; and expiration, in which an object reference is only valid for a certain length of time, after which a client must obtain a new reference. The implementation of these solutions is beyond the scope of this manual.

Obtaining the POA for a Servant

As mentioned in the previous sections, every servant inherits a `_default_POA` function from its skeleton class. The default implementation of this function returns the Root POA. If you instantiate servants on anything but the Root POA, you must override the function in the servant; otherwise, calls to `_this` will create incorrect object references. Usually, this involves remembering the POA reference for a servant in a private member variable and returning that reference from a call to `_default_POA`. (If all servants for objects of a particular interface type use the same POA, you can use a static member variable.)

In C++, you can use an approach similar to the following:

```
1 // C++
2 class Product_impl :
3     public virtual POA_Product,
4     public virtual PortableServer::RefCountServantBase
5 {
6     PortableServer::POA_var poa_;
7
8 public:
9     void Product_impl(PortableServer::POA_ptr poa)
10        : poa_(PortableServer::POA::_duplicate(poa))
11    {
12    }
13
14    virtual PortableServer::POA_ptr _default_POA()
15    {
16        return PortableServer::POA::_duplicate(poa_)
17    }
18 };
```

Lines 9-12 The constructor accepts a POA reference and remembers that reference in a private member variable.

Lines 14-17 The `_default_POA` function returns the servant's POA.

In Java, the approach is very similar:

```
// Java
public class Product_impl extends ProductPOA
{
private org.omg.PortableServer.POA poa_;

public Product_impl(org.omg.PortableServer.POA poa)
{
poa_ = poa;
}

public org.omg.PortableServer.POA
_default_POA()
{
return poa_;
}
}
```

Getting the POA for a Currently Executing Request

The ORB provides access to an object of type `PortableServer::Current`:

```
// IDL
module PortableServer
{
    interface Current : CORBA::Current
    {
        exception NoContext { };
        POA get_POA() raises(NoContext);
        ObjectId get_object_id() raises(NoContext);
    };
};
```

This interface provides access to the POA and the object ID for an executing request. Note that these operations must be invoked only from within the context of an executing operation inside a servant; otherwise, they raise `NoContext`. The `Current` object provides a useful way to obtain access to a servant's POA and object ID without having to store the POA reference in a member variable, at the cost of being accessible only from within an operation implementation. You can obtain a reference to the `Current` object from `resolve_initial_references`. In C++, the code looks something like this:// C++

```
// C++
CORBA::ORB_var orb = ... // Get the ORB somehow
CORBA::Object_var obj =
    orb -> resolve_initial_references("POACurrent");
PortableServer::Current_var current =
    PortableServer::Current::_narrow(obj);
if(!CORBA::is_nil(current))
    ... // Got Current object OK
```

You can keep the reference to the `Current` object in a variable and use it from within any executing operation in a servant. There is no need to refresh the `Current` reference for the current operation, not even for threaded servers. The ORB takes care of ensuring that operation invocations on the `Current` object return the correct data.

In Java, the code to obtain the `Current` reference looks like this:

```
// Java
org.omg.CORBA.ORB orb = ... // Get the ORB somehow
org.omg.CORBA.Object obj =
    orb.resolve_initial_references("POACurrent");
org.omg.PortableServer.Current current =
    org.omg.PortableServer.CurrentHelper.narrow(obj);
if(current != null)
    ... // Got Current object OK
```


Locating Objects

This chapter describes how to locate CORBA servant objects.

In this chapter

This chapter contains the following sections:

Obtaining Object References	page 148
Lifetime of Object References	page 152
Stringified Object References	page 156
Object Reference URLs	page 160
The BootManager	page 166
Initial Services	page 170
The IORDump utility	page 176

Obtaining Object References

Using CORBA, an object can obtain a reference to another object in a multitude of ways. One of the most common ways is by receiving an object reference as the result of an operation, as demonstrated by the following example:

```
1 // IDL
2 interface A
3 {
4 };
5
6 interface B
7 {
8 A getA();
9 };
```

Lines 2-4 An interface `A` is defined.

Lines 6-9 An interface `B` is defined with an operation returning an object reference to an `A`.

On the server side, `A` and `B` can be implemented in C++ as follows:

```

1 // C++
2 class A_impl : public POA_A,
3               public PortableServer::RefCountServantBase
4 {
5 };
6
7 class B_impl : public POA_B,
8               public PortableServer::RefCountServantBase
9 {
10     A_impl* a_;
11
12 public:
13
14     B_impl()
15     {
16         a_ = new A_impl();
17     }
18
19     ~B_impl()
20     {
21         a_ -> _remove_ref();
22     }
23
24     virtual A_ptr getA() throw(CORBA::SystemException)
25     {
26         return a_ -> _this();
27 };

```

Lines 2-5 The servant class `A_impl` is defined, which inherits from the skeleton class `POA_A` and the class `RefCountServantBase` which provides a reference counting implementation.

Lines 7-28 The servant class `B_impl` inherits from the skeleton class `POA_B` and the reference counting class `RefCountServantBase`.

Lines 14-17 An instance of the servant class `A_impl` is created in the constructor for `B_impl`.

Lines 19-22 In the destructor for `B_impl`, the reference count for the servant `A_impl` is decremented, which leads to the destruction of the servant.

Lines 24-27 `getA` returns an object reference to the `A_impl` servant (implicitly creating and activating the CORBA object if necessary).

In Java, the interfaces can be implemented like this:

```

1 // Java
2 public class A_impl extends APOA
3 {
4 }
5
6 public class B_impl extends BPOA
7 {
8     org.omg.CORBA.ORB orb_;
9     A_impl a_;
10
11     public B_impl(org.omg.CORBA.ORB orb)
12     {
13         orb_ = orb;
14         a_ = new A_impl();
15     }
16
17     A getA()
18     {
19         return a_._this(orb_);
20     }
21 }

```

Lines 2-4 The servant class `A_impl` is defined, which inherits from the skeleton class `APOA`.

Lines 6-21 The servant class `B_impl` is defined, which inherits from the skeleton class `BPOA`.

Lines 11-15 `B_impl`'s constructor stores a reference to the orb and creates a new `A_impl` servant.

Lines 17-20 `getA` returns an object reference to the `A_impl` servant (implicitly creating and activating the CORBA object if necessary).

A client written in C++ could use code like the following to get references to A:

```

// C++
B_var b = ... // Get a B object reference somehow
A_var a = b -> getA();

```

And in Java:

```
// Java
B b = ... // Get a B object reference somehow
A a = b.getA();
```

In this example, once your application has a reference to a `B` object, it can obtain a reference to an `A` object using `getA`. The question that arises, however, is How do I obtain a reference to a `B` object? This chapter answers that question by describing a number of ways an application can *bootstrap* its first object reference.

Lifetime of Object References

All of the strategies described in this chapter involve the publication of an object reference in some form. A common source of problems for newcomers to CORBA is the lifetime and validity of object references. Using IIOP, an object reference can be thought of as encapsulating several pieces of information:

- hostname
- port number
- object key

If any of these items were to change, any published object references containing the old information would likely become invalid and its use might result in a `TRANSIENT` or `OBJECT_NOT_EXIST` exception. The sections that follow discuss each of these components and describe the steps you can take to ensure that a published object reference remains valid.

Hostname

By default, the hostname in an object reference is the canonical hostname of the host on which the server is running. Therefore, running the server on a new host invalidates any previously published object references for the old host.

Orbacus provides the `-IIOPhost` option to allow you to override the hostname in any object references published by the server. This option can be especially helpful when used in conjunction with the Domain Name System (DNS), in which the `-IIOPhost` option specifies a hostname alias that is mapped by DNS to the canonical hostname.

See [“Command-line Options and Endpoints” on page 105](#) for more information on the `-IIOPhost` option.

Port Number

Each time a server is executed, the Root POA manager selects a new port number on which to listen for incoming requests. Since the port number is included in published object references, subsequent executions of the server could invalidate existing object references.

To overcome this problem, Orbacus provides the `-IIOPport` option that causes the Root POA manager to use the specified port number. You will need to select an unused port number on your host, and use that port number every time the server is started.

See [“Command-line Options and Endpoints” on page 105](#) for more information on the `-IIOPport` option.

Object Key

Each object created by a server is assigned a unique key that is included in object references published for the object. Furthermore, the order in which your server creates its objects may affect the keys assigned to those objects. To ensure that your objects always have the same keys, activate your objects using POAs with the `PERSISTENT` life span policy and the `USER_ID` object identification policy.

Stringified Object References

The CORBA specification defines two operations on the ORB interface for converting object references to and from strings.

```
// IDL
module CORBA
{
    interface ORB
    {
        string object_to_string(in Object obj);
        Object string_to_object(in string ref);
    };
};
```

Using stringified object references is the simplest way of bootstrapping your first object reference. In short, the server must create a stringified object reference for an object and make the string available to clients. A client obtains the string and converts it back into an object reference, and can then invoke on the object.

The examples discussed in the sections below are based on the IDL definitions presented at the beginning of this chapter.

Using a File

One way to publish a stringified object reference is for the server to create the string using `object_to_string` and then write it to a well-known file. Subsequently, the client can read the string from the file and use it as the argument to `string_to_object`. This method is shown in the following C++ and Java examples.

First, we'll look at the relevant server code:

```
1 // C++
2 CORBA::ORB_var orb = ... // Get a reference to the ORB somehow
3 B_impl* bImpl = new B_impl();
4 PortableServer::ServantBase_var servant = bImpl;
5 B_var b = bImpl -> _this();
6 CORBA::String_var s = orb -> object_to_string(b);
7 ofstream out("object.ref")
8 out << s << endl;
9 out.close();
```

Lines 3-5 A servant for the interface `B` is created and is used to incarnate a CORBA object.

Line 6 The object reference of the servant is stringified.

Lines 7-9 The stringified object reference is written to a file.

In Java, the server code looks like this:

```
1 // Java
2 org.omg.CORBA.ORB orb = ... // Get a reference to the ORB
  somehow
3 B_impl bImpl = new B_impl();
4 B b = bImpl._this(orb);
5 String ref = orb.object_to_string(b);
6 java.io.PrintWriter out = new java.io.PrintWriter(
7     new java.io.FileOutputStream("object.ref"));
8 out.println(ref);
9 out.close();
```

Lines 3-4 A servant for the interface `B` is created and is used to incarnate a CORBA object.

Line 5 The object reference of the servant is stringified.

Lines 6-9 The stringified object reference is written to a file.

Now that the stringified object reference resides in a file, our clients can read the file and convert the string to an object reference:

```
1 // C++
2 CORBA::ORB_var orb = ... // Get a reference to the ORB somehow
3 ifstream in("object.ref");
4 string s;
5 in >> s;
6 CORBA::Object_var obj = orb -> string_to_object(s.c_str());
7 B_var b = B::_narrow(obj);
```

Lines 3-5 The stringified object reference is read.

Line 6 `string_to_object` creates an object reference from the string.

Line 7 Since the return value of `string_to_object` is of type `CORBA::Object_ptr`, `B::_narrow` must be used to get a `B_ptr` (which is assigned to a self-managed `B_var` in this example).

```
// Java
org.omg.CORBA.ORB orb = ... // Get a reference to the ORB somehow
java.io.BufferedReader in = new java.io.BufferedReader(
    new java.io.FileReader("object.ref"));
String ref = in.readLine();
org.omg.CORBA.Object obj = orb.string_to_object(ref);
B b = BHelper.narrow(obj);
```

Lines 3-5 The stringified object reference is read.

Line 6 `string_to_object` creates an object reference from the string.

Line 7 Use `BHelper.narrow` to narrow the return value of `string_to_object` to `B`.

Using a URL

It is sometimes inconvenient or impossible for clients to have access to the same filesystem as the server in order to read a stringified object reference from a file. A more flexible method is to publish the reference in a file that is accessible by clients as a URL. Your clients can then use HTTP or FTP to obtain the contents of the file, freeing them from any local filesystem requirements. This strategy only requires that your clients know the appropriate URL, and is especially suited for use in applets.

Note: This example is shown only in Java because of Java's built-in support for URLs, but the strategy can also be used in C++.

```
1 // Java
2 import java.io.*;
3 import java.net.*;
4
5 String location = "http://www.mywebserver/object.ref";
6 org.omg.CORBA.ORB orb = ... // Get a reference to the ORB
   somehow
7
8 URL url = new URL(location);
9 URLConnection conn = url.openConnection();
10 BufferedReader in = new BufferedReader(
11     new InputStreamReader(conn.getInputStream()));
12 String ref = in.readLine();
13 in.close();
14
15 org.omg.CORBA.Object object = orb.string_to_object(ref);
16 B b = BHelper.narrow(object);
```

Line 5 `location` is the URL of the file containing the stringified object reference.

Lines 8-13 Read the string from the URL connection.

Line 15 Convert the string to an object reference.

Line 16 Narrow the reference to a `B` object.

Object Reference URLs

Prior to the adoption of the Interoperable Naming Service (INS) [10], the only standard format for stringified object references was the cumbersome `IOR:` format. The INS introduced two new, more readable formats for object references that use a URL-like syntax. Object reference URLs can be passed to `string_to_object`, just like `IOR:` references. The two new URL formats are described in detail in the specification, but will be briefly discussed here. The optional `file:` URL format is also discussed, as well as the proprietary `relfile:` URL format.

corbaloc: URLs

The `corbaloc:` URL supports any number of protocols; the format of the URL depends on the protocol in use. The general format of a `corbaloc:` URL is shown below:

```
corbaloc:[protocol]:<protocol-specific>
```

Orbacus supports two standard protocols, `iiop` and `rir`, but additional protocols may be supported via transport plug-ins.

The `corbaloc:` URL for the `iiop` protocol has the following structure:

```
corbaloc:[iiop]:[version@]host[:port]/object-key
```

The components of the URL are as follows:

- `iiop` - This is the default protocol for `corbaloc:` URLs, and therefore is optional.
- `version` - The IIOp version number in `major.minor` format. The default is `1.0`.
- `host` - The hostname of the server.
- `port` - The port on which the server is listening. The default is `2089`.
- `object-key` - A stringified object key.

The specification allows a URL to contain multiple addresses, but the semantics are vendor-specific. In Orbacus, each address is used in turn until one is found that works or until the ORB has tried them all and failed to contact the object.

The `rir` protocol is a shortcut for the ORB operation `resolve_initial_references`. The `corbaloc:` URL for the `rir` protocol has the following structure:

```
corbaloc:rir:[/id]
```

The components of the URL are as follows:

- `rir` - The protocol.
- `id` - The identifier of the service to be resolved. The identifier `NameService` is used if `id` is not supplied.

Some examples of `corbaloc:` URLs are:

```
corbaloc::nshost:10000/NameService
corbaloc::myhost:10000/MyObjectId
corbaloc:rir:/NameService
```

See [“The BootManager” on page 166](#) for information on how a server can support corbaloc: URLs.

corbaname: URLs

A `corbaname:` URL provides additional flexibility by incorporating use of the Naming Service in the `string_to_object` operation. The `corbaname:` URL extends the capabilities of the `corbaloc:` URL to allow the `object-key` to identify a binding in a Naming Service. For example, consider this URL:

```
corbaname::ns1:5001/NameService#ctx/MyObject
```

When the ORB interprets this URL, it attempts to resolve a naming context object located at host `ns1` on port `5001` and having the object key `NameService`. Once the naming context has been resolved, the ORB attempts to lookup the binding named `MyObject` in the naming context `ctx`. If successful, the result of `string_to_object` is the object reference associated with the binding.

file: URLs

A `file:` URL provides a convenient way to obtain object references using an IOR or URL reference that is in a file. The format of a `file:` URL is:

```
file:<absolute file name>
```

Using the `file:` URL and given that the file `object.ref` is located in the `/tmp` directory, the client side example of on page 157 may be simplified as follows:

```
// C++
CORBA::ORB_var orb = ... // Get a reference to the ORB somehow
CORBA::Object_var obj
    = orb -> string_to_object("file:/tmp/object.ref");
B_var b = B::_narrow(obj);

// Java
org.omg.CORBA.ORB orb = ... // Get a reference to the ORB somehow
org.omg.CORBA.Object obj =
    orb.string_to_object("file:/tmp/object.ref");
B b = BHelper.narrow(obj);
```

refile: URLs

Orbacus also provides the proprietary `refile:` URL. This URL is the same as the `file:` URL except that it takes a relative file name instead of an absolute file name.

The BootManager

Consider the following `corbaloc:` URL:

```
corbaloc::myhost:10000/MyObjectId
```

In this example, `MyObjectId` is the complete object key. Normally, object keys require more information than a simple name to uniquely identify a POA and a servant within the POA. The CORBA specification does not standardize how a server can configure these simple object keys, therefore each ORB implementation must provide a proprietary solution. In Orbacus, the `BootManager` provides the mapping from a simple object key to a complete object reference.

BootManager Interface

Here is the IDL interface for the BootManager:

```
module OB
{
  local interface BootManager
  {
    exception NotFound {};
    exception AlreadyExists {};

    void add_binding(in PortableServer::ObjectId oid, in Object obj)
      raises(AlreadyExists);

    void remove_binding(in PortableServer::ObjectId oid)
      raises(NotFound);
  };
};
```

For the complete IDL description, please see [Appendix A](#).

How the BootManager Works

When an Orbacus server receives a request, the ORB verifies that the key has the ORB's internal format. If not, the ORB will ask the BootManager if it has a mapping for the foreign key. If a match is found, the ORB will return a location forward reply, redirecting the client to the object reference supplied by the BootManager.

Using the BootManager

The `BootManager::add_binding` operation binds an object id to an object reference. The `BootManager::remove_binding` operation removes an existing binding. The following example illustrates how a server can add a binding for the object id `MyObjectId`.

```

1 // C++
2 CORBA::Object_var obj = // ... Get a reference
3 CORBA::Object_var bmgrObj =
4   orb -> resolve_initial_references("BootManager");
5 OB::BootManager_var bootManager =
6   OB::BootManager::_narrow(bmgrObj);
7 PortableServer::ObjectId_var objId =
8   PortableServer::string_to_ObjectId("MyObjectId");
9 bootManager -> add_binding(objId, obj);

```

Lines 3-6 Get a reference to the `BootManager` object by invoking `resolve_initial_references` on the ORB.

Lines 7-8 Create the object id.

Line 9 Create the new binding.

And in Java:

```

// Java
org.omg.CORBA.Object obj = // ... Get a reference
org.omg.CORBA.Object bmgrObj =
  orb.resolve_initial_references("BootManager");
com.ooc.OB.BootManager_var bootManager =
  com.ooc.OB.BootManagerHelper.narrow(bmgrObj);
byte[] objId = "MyObjectId".getBytes();
bootManager.add_binding(objId, obj);

```

Lines 3-6 Get a reference to the `BootManager` object by invoking `resolve_initial_references` on the ORB.

Line 7 Create the object id.

Line 8 Create the new binding.

Initial Services

The CORBA specification provides a standard way to bootstrap an object reference through the use of *initial services*, which denote a set of unique services whose object references, if available, can be obtained using the ORB operation `resolve_initial_references`, which is defined as follows:

```
// IDL
module CORBA
{
    interface ORB
    {
        typedef string ObjectId;
        exception InvalidName {};

        Object resolve_initial_references(in ObjectId identifier)
            raises(InvalidName);
    };
};
```

Initial services are intended to have well-known names, and the OMG has standardized the names for some of the CORBA services [9]. For example, the Naming Service has the name `NameService`, and the Trading Service has the name `TradingService`.

Resolving an Initial Service

An example in which the ORB is queried for a Naming Service object reference will demonstrate how to use `resolve_initial_references`. The example assumes that the ORB has already been initialized as usual. First the Java version:

```
1 // Java
2 org.omg.CORBA.Object obj = null;
3 org.omg.CosNaming.NamingContext ctx = null;
4
5 try
6 {
7     obj = orb.resolve_initial_references("NameService");
8 }
9 catch(org.omg.CORBA.ORBPackage.InvalidName ex)
10 {
11     ... // An error occurred, service is not available
12 }
13
14 if(obj == null)
15 {
16     ... // The object reference is invalid
17 }
18
19 try
20 {
21     ctx = org.omg.CosNaming.NamingContextHelper.narrow(obj);
22 }
23 catch(org.omg.CORBA.BAD_PARAM ex)
24 {
25     ... // This object does not implement a NamingContext
26 }
```

Lines 5-12 Try to resolve the name of a particular service. If a service of the specified name is not known to the ORB, an `InvalidName` exception is thrown.

Lines 19-26 The service type was known. Now the object reference has to be narrowed to the particular service type. If this fails, the service is not available.

And here's the C++ equivalent to the Java version above:

```
// C++
CORBA::Object_var obj;
CosNaming::NamingContext_var ctx;

try
{
    obj = orb -> resolve_initial_references("NameService");
}
catch(CORBA::ORB::InvalidName&)
{
    ... // An error occurred, service is not available
}

if(CORBA::is_nil(obj))
{
    ... // The object reference is invalid
}

ctx = CosNaming::NamingContext::_narrow(obj);
if(CORBA::is_nil(ctx))
{
    ... // This object does not implement NamingContext
}
```

Configuring the Initial Services

When an application uses initial services that are not locality-constrained, the application must register the object references for these objects with the ORB. Orbacus supports the standard `-ORBInitRef` and `-ORBDefaultInitRef` command-line options for registering initial service object references:

```
-ORBInitRef name=URL
-ORBDefaultInitRef URL
```

For example, starting an application as shown below will enable the client to resolve the `NameService` initial reference:

```
myclient -ORBInitRef NameService=corbaloc::nshost:10000/
NameService
```

The `-ORBconfig` option is an alternative method for defining a list of initial services, and is often preferable when a number of services must be defined.

See [“Configuring the ORB and Object Adapter” on page 77](#) for more information on these command-line options. Also refer to the INS specification [10] for detailed information on the standard options `-ORBInitRef` and `-ORBDefaultInitRef`.

In addition to using command-line parameters, a program can add to the list of initial services using the ORB operation `register_initial_reference`¹:

```
// IDL
module CORBA
{
    interface ORB
    {
        void register_initial_reference(in ObjectId id, in Object
obj)
            raises(InvalidName);
    };
};
```

For example, in C++:

```
1 // C++
2 CORBA::Object_var obj = ... // Get a name service reference
somehow
3 orb -> register_initial_reference("NameService", obj);
```

1. This will become part of the ORB interface when the Portable Interceptor specification is adopted.

Line 2 Get a reference to the naming service, for example by reading a stringified object reference and converting it with `string_to_object`, or by any other means.

Line 3 Add the reference to the ORB's list of initial references.

Or in Java:

```
// Java
org.omg.CORBA.Object obj = ...// Get a name service reference
    somehow
orb.register_initial_reference("NameService", obj);
```

This is the same as the C++ version above.

The Initial Service Locator

In addition to providing the Orbacus Implementation Repository, the IMR server (see [Chapter 7](#)) acts as an initial service locator. That is, assuming that the IMR server is properly configured, the name of the host running the IMR server is the only information needed to find a particular initial service.

To locate an initial service with name `foo`, the IMR server must first be configured with the initial reference of this service. This may be done with the `-ORBInitRef` command-line option or the `ooc.orb.service` configuration property (see [Chapter 4](#) for details). Next, the client that wishes to connect to `foo` must be configured with the default initial reference specifying the host running the IMR server. The `-ORBDefaultInitRef` command-line option or the `ooc.orb.default_init_ref` configuration property may be used to configure the default initial reference. For example, given that the IMR server is running on `imr-host`, then the client can be started with the option:

```
-ORBDefaultInitRef=corbaloc::imr-host
```

When the client is configured with this default initial reference it may invoke `resolve_initial_references("foo")` on the ORB to obtain a reference to `foo`.

The IORDump utility

Overview

Orbacus provides the `iordump` utility to decode stringified IORs and to print out their components in human readable format. It is available in a C++ and a Java version.

Its usage is shown below. For C++:

```
iordump [options] [-f FILE ... | IOR ...]
```

For Java:

```
com.ooc.OB.IORDump [options] [-f FILE ... | IOR ...]
```

<code>-h, --help</code>	Show available options.
<code>-v, --version</code>	Show Orbacus version.
<code>-f FILE ...</code>	Read IORs from file instead of command line.
<code>IOR ...</code>	List of IORs.

The Java version is available in `OB.jar`.

Sample output for the demo/hello example

The following command:

```
iordump -f Hello.ref
```


prints:

```

IOR #1:
byteorder: little endian
type_id: IDL:Hello:1.0
Profile #1: iiop
iiop_version: 1.2
host: 192.168.0.1
port: 17000
object_key: (37)
171 172 171 49 49 48 50 48 "...11020"
 55 55 53 54 56 48 0 95 "775680_"
 82 111 111 116 80 79 65 0 "RootPOA."
 0 202 254 186 190 60 215 205 "...||¥<î."
 0 0 0 0 0 "....."
Native char codeset:
"ISO 8859-1:1987; Latin Alphabet No. 1"
Char conversion codesets:
"ISO 646:1991 IRV (International Reference Version)"
"X/Open UTF-8; UCS Transformation Format 8 (UTF-8)"
Native wchar codeset:
"ISO/IEC 10646-1:1993; UCS-2, Level 1"
Wchar conversion codesets:
"ISO/IEC 10646-1:1993; UTF-16, UCS Transformation Format 16-bit form"

```


The Implementation Repository

This chapter describes how the Orbacus Implementation Repository (IMR) works and how to use it.

In this chapter

This chapter contains the following sections:

Background	page 181
Information Managed by the IMR	page 182
IMR Security	page 185
Usage	page 186
Windows Native Service	page 188
Configuration Properties	page 190
Connecting to the Service	page 191
Utilities	page 192
Getting Started with the Implementation Repository	page 195

Background

Overview

The Orbacus Implementation Repository (IMR) provides support for the indirect binding¹ of persistent object references. The key advantage of indirect binding is that it loosens the coupling between clients and servers so that the location of the server can change without affecting the client. In practical terms, this is accomplished by providing the client with an IOR that actually refers to the IMR, rather than to the server itself. The IMR also provides the ability to start servers on demand using the Object Activation Daemon (OAD).

The CORBA specification does not standardize how servers and the IMR interact, it only suggests functionality for vendors to implement. Hence, the interface between servers and the IMR is strictly proprietary. Due to the proprietary interface between servers and the IMR, servers using the IMR must be developed using Orbacus for C++ or Java. However, the interaction between clients and the IMR is strictly specified by the GIOP specification, so any client that is CORBA compliant may interact with the IMR.

How It All Works

When a server is using the IMR, object references created by one of its persistent POAs refer to the IMR rather than to the server itself. When the client makes a request using this reference, the IMR receives the request, activates the server (if necessary) using the OAD, and returns a new object reference to the client that identifies the server at its current host and port. The client then establishes a connection with the server using the new object reference and communicates directly with the server, without the intervention of the IMR. However, should the server fail, a well-behaved client will contact the IMR again, which may restart the server and allow the client to resume its activities.

1. Binding refers to the process of opening a connection and associating an object reference with its servant.

Information Managed by the IMR

The IMR provides support for the indirect binding and automatic activation of servers within a given domain. In order to provide this support, the IMR manages three types of entities: OADs, servers, and POAs.

OADs

An OAD is responsible for the activation of servers on a given host. Each OAD is registered in the IMR using a host name. The IMR also maintains the status of each OAD. If the OAD is running and in a ready state it will have a status of `up`, otherwise, its status will be `down`.

Servers

Servers are registered with a name that is unique within the domain and the host corresponding to the OAD that is responsible for the server. Since the name is unique within the domain, it is not currently possible to register the same server with multiple OADs. The server name that is registered in the IMR can be any string, but it must be the same as the name used by the server (that is, the name specified by the `-ORBServerId` option, or equivalent property). The attributes of a server that are stored by the IMR are summarized below:

<code>host</code>	The host corresponding to the OAD that is responsible for the server.
<code>exec</code>	The path of server executable (the <code>.exe</code> extension must be included on Windows platforms). If this attribute is not set, then the IMR will not activate the server.
<code>args</code>	The arguments to be supplied when starting the server executable. Note that <code>-ORBServerId server-id</code> is automatically appended to the arguments before the server process is started.
<code>rundir</code>	The directory that the server process will be started from. If this attribute is not set, then the server process will be started from the root directory. For Windows platforms, the full path must be specified in the <code>exec</code> attribute even if this attribute is set.

<code>mode</code>	The activation mode. The possible values are: <code>shared</code> , only one server process is created which is used by all clients, and <code>persistent</code> , the server process is started when the IMR starts and is used by all clients.
<code>activate-poas</code>	If this attribute is set to <code>true</code> (default), then all persistent POAs will be registered automatically. If set to <code>false</code> , then persistent POAs are not registered automatically.
<code>update-timeout</code>	The amount of time (in milliseconds) to wait for server status updates.
<code>failure-timeout</code>	The amount of time (in seconds) to wait for the server to start.
<code>max-spawns</code>	The maximum number of tries to start the server.

The IMR also maintains various state information for each server:

- The internal ID of the server.
- The status of the server process. The valid values are `forked`, `starting`, `running`, `stopping`, and `stopped`.
- Whether or not the server was started manually.
- The number of times that the server process has been spawned.

Server processes inherit environment settings from the environment in which the OAD was started. Hence, `path`, `library path`, and `class path` environment variables can be used by the server application. This is especially useful in the case of shared library and class path settings. (Note that the class path may also be set in the `args` attribute.)

On Windows platforms, the `exec` attribute may refer to an executable or batch file. Make sure that the first line of the batch file contains:

```
@echo off
```

On UNIX platforms, the `exec` attribute may refer to an executable or a shell script with

```
#!/interpreter
```

as its first line.

However, if a batch file or shell script is used, then it should accept the `-ORBServerId` option since it is automatically appended to the `args` attribute by the IMR.

In the case of Java servers, a batch file or shell script should be created to start the server. An alternative is to set the `exec` attribute to the Java interpreter and to use the `args` attribute to specify the class implementing the server.

POAs

The IMR allows implicit registration of POAs when the server is started. This can be enabled or disabled for each server using the `activate_poas` server attribute. If implicit registration is enabled, then the user does not have to register any of the POAs; instead, the server transparently notifies the IMR whenever a call to `create_POA` is made by the application code.

If the user disables implicit registration, then the user must register all persistent POAs (that is, POAs with the `PERSISTENT` life span policy). POAs are registered using the name of its server and the name of the POA. Note that any transient POAs (POAs with the `TRANSIENT` life span policy) created by the server are not registered with the IMR.

The IMR also maintains the status for each POA, which indicates the state of its POA Manager. The valid values are `inactive`, `active`, `holding`, and `discarding`.

IMR Security

It is *very important* that *only* the IMR's public endpoint (also referred to as its forward endpoint) be accessible outside of the network firewall. Otherwise, anyone can mimic the IMR and cause an OAD to run any command they decide.

For additional security, the information managed by the IMR may only be modified when the IMR is running in *administrative* mode. That is:

- OAD registration and removal,
- server registration and removal,
- modification of server attributes, and
- POA registration and removal

are only possible when the IMR is running in administrative mode. An attempt to modify the information managed by the IMR when it is not running in administration mode will result in a `CORBA:NO_PERMISSION` exception.

Usage

The IMR and OAD are currently implemented using Orbacus for C++, but Orbacus for Java servers can also be launched by the IMR. Both the IMR and OAD are contained in the IMR server, which may be started in one of three modes:

master	Start only the IMR.
slave	Start only the OAD.
dual	Start both the IMR and OAD.

Command-line usage is as follows:

```
imr
[-h,--help] [-v,--version] [-m,--master] [-s,--slave]
[-a,--administrative] [-d,--database] [-A,--admin-endpoint]
[-F,--forward-endpoint] [-S,--slave-endpoint]
[-L, --locator-endpoint]
```

-h --help	Display the command-line options supported by the server.
-v --version	Display the version of the server.
-m --master	Run the server in <code>master</code> mode. ^a
-s --slave	Run the server in <code>slave</code> mode. ^a
-a --administrative	Run the IMR in administrative mode. The IMR will run in non-administrative mode by default.
-d DIRECTORY --database DIRECTORY	Specifies the directory in which the IMR maintains its database files. If not specified, the current working directory is used.

<p>-A INFO --admin-endpoint INFO</p>	<p>Specifies the IMR's administrative endpoint settings. This is the endpoint that the OADs and IMR-enabled servers use to communicate with the IMR. For security reasons, access to this endpoint can be restricted. If not specified, <code>iiop --port 9999</code> is used.</p>
<p>-F INFO --forward-endpoint INFO</p>	<p>Specifies the IMR's public endpoint, which is used by clients for server requests. If not specified, <code>iiop --port 9998</code> is used.</p>
<p>-S INFO --slave-endpoint INFO</p>	<p>Specifies the endpoint used by the OAD. Note that all of the OADs in a domain must use the same endpoint. If not specified, <code>iiop --port 9997</code> is used.</p>
<p>-L INFO --locator-endpoint INFO</p>	<p>Specifies the endpoint used by the Initial Service Locator (see "The Initial Service Locator" on page 175). If not specified, <code>iiop --port 2809</code> is used.</p>

a. Note that only one of the `-m` or `-s` options may be specified. Also, if neither the `-m` or `-s` option is specified, then the server is started in `dual` mode.

Windows Native Service

The IMR server is also available as a native Windows service.

```
ntimrservice
[-h,--help] [-i,--install] [-s,--start-install]
[-u,--uninstall] [-d,--debug]
```

-h --help	Display the command-line options supported by the service.
-i --install	Install the service. The service must be started manually.
-s --start-install	Install and start the service.
-u --uninstall	Uninstall the service.
-d --debug	Run the service in debug mode.

In order to use the IMR server as a native Windows service, first add the desired configuration properties to the `HKEY_LOCAL_MACHINE` NT registry key (see [“Using the Windows Registry” on page 91](#) for more details). For example, add the `ooc.imr.admin_endpoint`, `ooc.imr.forward_endpoint`, and `ooc.imr.slave_endpoint` properties so that the IMR and OAD will use non-default endpoint settings.

Next the service should be installed with:

```
ntimrservice -i
```

This adds the `Orbacus Implementation Repository` entry to the `Services` dialog in the `Control Panel`. To start the service, select the `Orbacus Implementation Repository` entry, and press `Start`. If the service is to be started automatically when the machine is booted, select the `Orbacus Implementation Repository` entry, then click `Startup`. Next select `Startup Type - Automatic`, and press `OK`. Alternatively, the service could have been installed using the `-s` option, which configures the service for automatic start-up:

```
ntimrservice -s
```

If you want to remove the service, run:

```
ntimrservice -u
```

Note: If the executable for the service is moved, it must be uninstalled and re-installed.

Any trace information provided by the service is placed in the Windows Event Viewer with the title `IMRService`. To enable tracing information, add the desired trace configuration property (that is, one of the `ooc.imr.trace` properties or one of the `ooc.orb.trace` properties) to the

`HKEY_LOCAL_MACHINE` NT registry key with a `REG_SZ` value of at least 1.

Configuration Properties

In addition to the standard configuration properties described in [Chapter 4](#), the IMR also supports the following properties:

Property	Value	Description
ooc.imr.mode	<code>master, slave, dual</code>	Specifies the mode in which the imr server will be started.
ooc.imr.administrative	<code>true, false</code>	If set to <code>true</code> , then run the IMR in administrative mode. For details refer to the <code>-a</code> command-line option.
ooc.imr.dbdir	<i>directory</i>	Equivalent to the <code>-d</code> command-line option.
ooc.imr.admin_endpoint	<i>info</i>	Equivalent to the <code>-A</code> command-line option.
ooc.imr.forward_endpoint	<i>info</i>	Equivalent to the <code>-F</code> command-line option.
ooc.imr.slave_endpoint	<i>info</i>	Equivalent to the <code>-s</code> command-line option.
ooc.imr.locator_endpoint	<i>info</i>	Equivalent to the <code>-L</code> command-line option.
ooc.imr.trace.peer_status	<i>level</i> >= 0	Defines the output level for IMR diagnostic messages related to communications with the OADs. The default level is 0, which produces no output.
ooc.imr.trace.process_control	<i>level</i> >= 0	Defines the output level for IMR diagnostic messages related to the forking and death of server processes. The default level is 0, which produces no output.
ooc.imr.trace.server_status	<i>level</i> >= 0	Defines the output level for IMR diagnostic messages related to the status of servers and POAs. The default level is 0, which produces no output.

Connecting to the Service

Servers that use the IMR must be configured with the IMR initial reference. The object key of the IMR is `IMR`, hence, a URL-style object reference of the IMR service running on host `imrhost` at port `10000` would be:

```
corbaloc::imrhost:10000/IMR
```

Using this object reference, a server can configure the IMR initial reference with the property:

```
ooc.orb.service.IMR=corbaloc::imrhost:10000/IMR
```

An alternative to using the above property is to use the `-ORBInitRef` command-line option. Refer to [Chapter 6](#) for more information on URLs and configuring initial services.

Utilities

Implementation Repository Administration

The `imradmin` utility provides complete control over the IMR, OADs and servers in a domain. Its command interface is shown below:

<code>-h, --help</code>	Display this information.
<code>--add-oad [host]</code>	Register an OAD for the specified host.
<code>--add-server server-name [exec [host]]</code>	Register a server under the OAD specified by <i>host</i> with the given <i>exec</i> attribute.
<code>--add-poa server-name poa-name</code>	Register a POA for the specified server.
<code>--remove-oad [host]</code>	Unregister an OAD.
<code>--remove-server server-name</code>	Unregister a server.
<code>--remove-poa server-name poa-name</code>	Unregister a POA.
<code>--get-oad-status [host]</code>	Get the status of an OAD.
<code>--get-server-info server-name</code>	Get the attributes and state information for a server.
<code>--get-poa-status server-name poa-name</code>	Get the status of a POA.
<code>--list-oads</code>	List all OADs.
<code>--list-servers</code>	List all servers.
<code>--list-poas server-name</code>	List all POAs.
<code>--tree</code>	Display all OADs, servers and POAs in a tree like format.
<code>--tree-oad [host]</code>	Display an OAD and its associated servers and POAs in a tree like format.
<code>--tree-server server-name</code>	Display a server and its associated POAs in a tree like format.

<code>--set-server <i>server-name</i> {exec host args rundir mode activate_poas update_timeout failure_timeout max_spawns} <i>value</i></code>	Set an attribute of a server. For example, <code>--set-server srv max_spawns 2</code> sets the <code>max_spawns</code> attribute for the server <code>srv</code> to 2.
<code>--start-server <i>server-name</i></code>	Start a server.
<code>--stop-server <i>server-name</i></code>	Stop a server.
<code>--reset-server <i>server-name</i></code>	Reset a server.

Note that the `imradmin` utility also needs to be configured with the IMR initial reference (see [“Connecting to the Service” on page 191](#)).

The `host` argument is optional. If `host` is not specified the local host name is used. The `server-name` argument refers to the name of the server. The format of the `poa-name` argument is `poa1/poa2/poa3`, where `poa1` is a child of the Root POA, `poa2` is a child of `poa1`, and `poa3` is a child of `poa2`. Refer to [“Information Managed by the IMR” on page 182](#) for further details.

In very rare circumstances, it's possible for the IMR and OAD to become confused as to the state of a server. In this case it might be necessary to manually reset the state of the server using the `--reset-server` command. It is also necessary to use this command if the server continually crashes on startup and has reached the maximum number of retries specified by its `max_spawns` attribute. This prevents the OAD from continually starting the same broken server.

Making References

The `mkref` utility creates IMR-based object references for use by clients. Since the Object ID is required to create a reference, this utility can only be used to create references for objects created by POAs using the `USER_ID` object identification policy. Its usage is shown below.

```
mkref [-H host] [-P port] server-name object-id poa1/poa2/
.../poan
```

<i>host</i>	The host that the <code>imr</code> server is running on. The default value is the canonical hostname of the machine in which <code>mkref</code> is executed.
-------------	--

<i>port</i>	The forward port of the <code>imr</code> server. If not set, then <code>mkref</code> will use 9998.
<i>server-name</i>	The name of the server as registered in the IMR.
<i>object-id</i>	The Object ID used by the object.
<i>poa1/poa2/.../poan</i>	The POA which creates the object, where <i>poa1</i> is a child of the Root POA, <i>poa2</i> is a child of <i>poa1</i> , and so on.

Upgrading the IMR Database

The `imrdbupgrade` utility is used to upgrade an earlier version of the IMR database. Command-line usage is as follows:

```
imrdbupgrade database-directory
```

The *database-directory* parameter is used to specify the IMR database directory.

Getting Started with the Implementation Repository

To use the IMR, several steps must be taken. These steps are presented below and are explained by way of example. In this example we assume that Orbacus has been installed in the directory `/usr/local/Orbacus` and the executables `imr`, `imradmin` and `mkref` all exist in a directory that is in the search path.

1. Determine the physical architecture.

In this example, we have a network with three hosts: `master`, `slave1` and `slave2`. The host `master` is used to run only the IMR. The hosts `slave1` and `slave2` are used to run individual CORBA servers.

2. Create a configuration file for the IMR and OADs.

First, create a configuration file for the IMR containing the following:

```
# imr.conf
oc.oc.imr.admin_endpoint=iiop --port 10000
oc.oc.imr.forward_endpoint=iiop --port 10001
oc.oc.imr.slave_endpoint=iiop --port 10002
oc.oc.imr.mode=master
oc.oc.imr.dbdir=/usr/local/Orbacus/db
```

This file is placed in the `/usr/local/Orbacus/etc` directory on host `master`.

Second, create a configuration file for the OADs containing the following:

```
# oad.conf
oc.oc.orb.service.IMR=corbaloc::master:10000/IMR
oc.oc.imr.slave_endpoint=iiop --port 10002
oc.oc.imr.mode=slave
oc.oc.imr.dbdir=/usr/local/Orbacus/db
```

This files is placed in the `/usr/local/Orbacus/etc` directory on hosts `slave1` and `slave2`.

3. Start the IMR in administrative mode.

On host `master`, run:

```
imr -ORBconfig /usr/local/Orbacus/etc/imr.conf
--administrative
```

4. Start the OADs.

On host `slave1`, run:

```
imr -ORBconfig /usr/local/Orbacus/etc/oad.conf
```

On host `slave2`, run:

```
imr -ORBconfig /usr/local/Orbacus/etc/oad.conf
```

Each OAD automatically registers itself with the IMR. Note that an OAD can also be registered manually using the `imradmin` utility. For example, to register the OAD on host `slave1`, run:

```
imradmin -ORBInitRef IMR=corbaloc::master:10000/IMR \
--add-oad slave1
```

5. Add each server to the IMR.

In our example, we will run one server on each OAD. The server names are `Server1` and `Server2` and are located in `/usr/local/bin` on their respective hosts.

First, we register the servers using the `imradmin` utility:

```
imradmin -ORBInitRef IMR=corbaloc::master:10000/IMR \
--add-server Server1 "/usr/local/bin/server1" slave1
imradmin -ORBInitRef IMR=corbaloc::master:10000/IMR \
--add-server Server2 "/usr/local/bin/server2" slave2
```

Next, we set the server arguments:

```
imradmin -ORBInitRef IMR=corbaloc::master:10000/IMR \
--set-server Server1 args \
"-ORBInitRef IMR=corbaloc::master:10000/IMR"
imradmin -ORBInitRef IMR=corbaloc::master:10000/IMR \
--set-server Server2 args \
"-ORBInitRef IMR=corbaloc::master:10000/IMR"
```

A C++ server can automatically register itself with the IMR using the `-ORBregister` command-line option. For example, to register `Server1`, run the following on `slave1`:

```
/usr/local/bin/server1 -ORBregister Server1 \
-ORBInitRef IMR=corbaloc::master:10000/IMR
```

If the server requires command-line options, then these options must be added using the `imradmin` utility.

6. Add each POA to the IMR.

In this example, the servers are registered without setting the `activate_poas` attribute, so the attribute defaults to `true`. Hence, all

persistent POAs will be registered automatically. If this were not the case, the POAs would have to be registered manually.

7. Configure your servers to use the IMR.

There are three ways to configure a server to use the IMR:

- i. Use the `-ORBregister` command-line option (only available for C++ servers). This option is used for server registration and can only be used when starting the server for the first time.
- ii. Use the `-ORBServerId` command-line option.
- iii. Use the `ocf.orb.server_name` configuration property. This configuration property is equivalent to the `-ORBServerId` command-line option and may be set in a configuration file or programmatically prior to initializing the ORB in a server.

In this example, the IMR is responsible for starting the servers. Hence, when the server is started, the `-ORBServerId` option is automatically added to the argument list.

8. Create object references for use by the clients.

A server can always be used to create references for its objects.

However, if an object is created by a POA that uses the `USER_ID` object identification policy, then the `mkref` utility can also be used to create a reference for the object. Using the `mkref` utility is discussed below.

Assume each server has a single primary object. `Server1` uses `Object1` for its Object ID and `Server2` uses `Object2`. Also, each server creates a persistent POA called `Main` to hold its objects. To create object references for these objects, run the following on `master`:

```
mkref -P 10001 Server1 Object1 Main > Object1.ref
mkref -P 10001 Server2 Object2 Main > Object2.ref
```

After all OADs, servers and POAs are registered, it is recommended to restart the IMR in non-administrative mode. This will prevent any accidental (or unauthorized) modifications.

Programming Example

In this section, we will show how to modify the C++ version of the Hello World server (see [Chapter 2](#)) to use a persistent object reference. This will allow the server to use the IMR for indirect binding. Modifications to the Java version of the server are similar. The code for both the C++ and Java persistent Hello World servers may be found in the `demo/hello_imr` directories of the Orbacus for C++ and Java distributions.

The Hello World server presented in Chapter uses the Root POA to activate its Hello servant. Since the Root POA uses the `TRANSIENT` life span policy, the object reference it creates will not be persistent. Hence, the Hello World server must be modified so that the Hello servant is activated using a child POA with the `PERSISTENT` life span policy. The new child POA will also use the `USER_ID` object identification policy so that the `mkref` utility may be used. Further, the Hello servant is no longer activated under the Root POA, so it becomes necessary for it to override the `_default_POA` method. The modified servant's class declaration is shown below:

```

1 // C++
2
3 #include <Hello_skel.h>
4
5 class Hello_impl : public POA_Hello,
6                   public PortableServer::RefCountServantBase
7 {
8     PortableServer::POA_var poa_;
9
10 public:
11     Hello_impl(PortableServer::POA_ptr);
12
13     virtual void say_hello() throw(CORBA::SystemException);
14
15     virtual PortableServer::POA_ptr _default_POA();
16 };

```

Line 8 Private member to store the servant's default POA.

Line 12 A constructor must be defined to allow the assignment of the servant's default POA.

Line 16 Declaration of the `_default_POA` method.

The remainder of the class declaration is unchanged. The definition of the constructor and `_default_POA` method follow:

```
// C++  
  
Hello_impl::Hello_impl(PortableServer::POA_ptr poa)  
: poa_(PortableServer::POA::_duplicate(poa))  
{  
}  
  
PortableServer::POA_ptr Hello_impl::_default_POA()  
{  
return PortableServer::POA::_duplicate(poa_);  
}
```

The modified portion of the server program is shown below:

```

1 // C++
2
3 int
4 run(CORBA::ORB_ptr orb, int argc)
5 {
6     CORBA::Object_var poaObj =
7         orb -> resolve_initial_references("RootPOA");
8     PortableServer::POA_var rootPoa =
9         PortableServer::POA::_narrow(poaObj);
10
11     PortableServer::POAManager_var manager =
12         rootPoa -> the_POAManager();
13
14     CORBA::PolicyList pl(2);
15     pl.length(2);
16     pl[0] = rootPOA -> create_lifespan_policy(
17         PortableServer::PERSISTENT);
18     pl[1] = rootPOA -> create_id_assignment_policy(
19         PortableServer::USER_ID);
20
21     PortableServer::POA_var helloPOA =
22         rootPOA -> create_POA("hello", manager, pl);
23
24     Hello_impl* helloImpl = new Hello_impl(helloPOA);
25     PortableServer::ServantBase_var servant = helloImpl;
26     PortableServer::ObjectId_var oid =
27         PortableServer::string_to_ObjectId("hello");
28     helloPOA -> activate_object_with_id(oid, servant);
29     Hello_var hello = helloImpl -> _this();
30
31     CORBA::String_var s = orb -> object_to_string(hello);
32     ofstream out("Hello.ref");
33     out << s << endl;
34     out.close();
35
36     manager -> activate();
37     orb -> run();
38
39     return 0;
40 }

```

Lines 14-22 Create a new POA using `PERSISTENT` life span policy and the `USER_ID` object identification policy.

Lines 24-25 Create the Hello servant.

Lines 26-27 Using the string "hello", create an object id.

Line 28 Activate the servant with the new POA.

The remainder of the code is unchanged.

The Implementation Repository Console

The Orbacus Implementation Repository (IMR) includes a graphical client for administering the service called the Orbacus IMR Console. The Orbacus IMR Console provides complete control over the IMR, OADs and servers in a domain.

In this chapter

This chapter contains the following sections:

Usage	page 204
The Menus	page 205

Usage

Syntax

Use the IMR console as follows:

```
com.ooc.IMRConsole.Main
  [--look CLASS] [--windows] [--motif] [--mac] [-h,--help]
```

<code>--look CLASS</code>	Use the specified look and feel class.
<code>--windows</code>	Use the Microsoft Windows look and feel (if available).
<code>--motif</code>	Use the Motif look and feel (if available).
<code>--mac</code>	Use the Macintosh look and feel (if available).
<code>-h</code> <code>--help</code>	Display the command-line options supported by the program.

CLASSPATH Requirements

The Orbacus IMR Console requires the classes in `OB.jar`, `OBIMR.jar` and `OBUtil.jar`.

Implementation Repository Service Lookup

In order to locate an IMR Service, the application uses the initial IMR Service, as provided to the ORB with options such as `-ORBservice` or `-ORBconfig`. If the service is not found, an error is displayed and the IMR Console exits.

The Menu

The menus provide access to all of the features of the application. In addition, the most common actions are also available in the toolbar, as well as in a popup menu that is displayed when pressing the right mouse button over an item in the binding table or context tree.

The File Menu

The **File** menu contains the **Exit** menu item, which is used to exit the Orbacus IMR Console.

The Edit Menu

The operations in the **Edit** menu provide the means for manipulating OADs, servers and POAs.

Create	Create a new OAD, server, or POA.
Modify	Modify the selected object.
Delete	Delete the selected object.
Cut	Move the selected server to the clipboard.
Paste	Insert the server contained in the clipboard under the selected OAD.
Start	Start the selected server.
Stop	Stop the selected server.
Reset	Reset the state of the selected server.

The **Create** menu item creates a child object under the selected object. OADs are created under the IMR Domain root object, servers are created under OADs, and POAs are created under servers.

The **Modify** menu item applies to all objects. However, servers are currently the only objects that have attributes that can be modified.

To delete an object, the **Delete** menu item is used. This operation recursively deletes all children under the selected item.

The **Cut** and **Paste** menu items only apply to servers and are used to move servers to different hosts. Note that OAD for the desired host must be selected when using **Paste**.

In very rare circumstances, it's possible for the IMR and OAD to become confused as to the state of a server. In this case it might be necessary to manually reset the state of the server using the **Reset** menu item. It also necessary to use this item if the server continually crashes on startup and has reached the maximum number of retries specified by its `max_spawns` attribute. This prevents the OAD from continually starting the same broken server.

The View Menu

The **View** menu contains the **Refresh** menu item. The **Refresh** menu item is used to update the console when the contents of the IMR have been changed from outside the console. Note that clicking or expanding an item will refresh the item.

The Toolbar and the Popup Menu

In addition to the operations offered by the menu bar, some frequently needed functions are available by icons located in the toolbar. The toolbar contains all of the items of the **Edit** menu and the **Refresh** item of the **View** menu. The toolbar is shown below.



When selecting an OAD, server or POA with the right mouse button, a popup menu with a choice of operations will be displayed as shown below.



This popup menu provides the same operations as the toolbar.

Orbacus Names

A CORBA object is often represented by an object reference in the form of a stringified IOR, a lengthy string that is difficult to read and cumbersome to use. It is much more natural to think of an object in terms of its name, which is a core feature of the CORBA Naming Service. In the Naming Service, objects are registered with a unique name, which can later be used to resolve their associated object references.

Orbacus Names is compliant with [10]. This chapter does not provide a complete description of the service. It only provides an overview, suitable to get you started. For more information, please refer to the specification.

In this chapter

This chapter contains the following sections:

Usage	page 211
Windows Native Service	page 213
Configuration Properties	page 215
Persistence	page 216
Connecting to the Service	page 217
Using the Naming Service with the IMR	page 218
Bindings	page 219

Name Resolution	page 221
Programming Example	page 222

Usage

Orbacus includes functionally equivalent implementations of the Naming Service in C++ and Java.

Syntax

For C++:

```
nameserv
  [-h,--help] [-v,--version] [-i,--ior] [-n,--no-updates]
  [-s,--start] [-d,--database FILE] [-l, --limit COUNT]
  [-t,--timeout MINS] [-c, --callback-timeout SECS]
```

For Java:

```
com.ooc.CosNaming.Server
  [-h,--help] [-v,--version] [-i,--ior] [-n,--no-updates]
  [-s,--start] [-d,--database FILE] [-l, --limit COUNT]
  [-t,--timeout MINS] [-c, --callback-timeout SECS]
```

Options

The options in the following table apply to both C++ and Java versions.

-h --help	Display the command-line options supported by the server.
-v --version	Display the version of the server.
-i --ior	Prints the stringified IOR of the server to standard output.
-n --no-updates	Disables automatic updates. That is, callbacks that notify interested clients of changes to the naming service.
-s --start	Use this option only when starting a persistent server using a new database.

<pre>-d FILE --database FILE</pre>	<p>Enables persistence for the server. All of the bindings created by the server will be saved to the specified file. If you are starting the server for the first time using this database, you must also use the <code>-s</code> command-line option.</p>
<pre>-l COUNT --limit COUNT</pre>	<p>Limits the number of bindings returned in the binding list by a call to <code>list()</code> to <code>COUNT</code> bindings. Using this option can reduce the memory requirements of the server.</p>
<pre>-t MINS --timeout MINS</pre>	<p>Specifies the timeout in minutes after which a persistent server automatically compacts its database. The default timeout is five minutes.</p>
<pre>-c SECS --callback-timeout SECS</pre>	<p>Specifies the timeout in seconds to be used for the Orbacus timeout policy (<code>OB::TimeoutPolicy</code>). The default timeout is five seconds. See Chapter 16 for more information.</p>

CLASSPATH Requirements

Orbacus Names for Java requires the classes in `OB.jar` and `OBNaming.jar`.

Windows Native Service

The C++ version of Orbacus Names is also available as a native Windows service.

```
ntnameservice
  [-h,--help] [-i,--install] [-s,--start-install]
  [-u,--uninstall] [-d,--debug]
```

-h --help	Display the command-line options supported by the server.
-i --install	Install the service. The service must be started manually.
-s --start-install	Install the service. The service will be started automatically.
-u --uninstall	Uninstall the service.
-d --debug	Run the service in debug mode.

In order to use the Naming Service as a native Windows service, it is first necessary to add the `ooc.naming.endpoint` configuration property to the `HKEY_LOCAL_MACHINE` NT registry key (see [“Using the Windows Registry”](#) on [page 91](#) for more details). If the service is to be persistent, the path to the database file must be stored in the following property:¹

```
HKEY_LOCAL_MACHINE\Software\OOC\Properties\ooc\naming\database
```

Next the service should be installed with:

```
ntnameservice -i
```

This adds the Orbacus Naming Service entry to the Services dialog in the Control Panel. To start the naming service, select the Orbacus Naming Service entry, and press Start. If the service is to be started automatically when the machine is booted, select the Orbacus Naming Service entry,

1. Please note that services do not have access to network drives, so the path to the database must be on a local hard drive.

then click `Startup`. Next select `Startup Type - Automatic`, and press `OK`. Alternatively, the service could have been installed using the `-s` option, which configures the service for automatic start-up:

```
ntnameservice -s
```

If you want to remove the service, run:

```
ntnameservice -u
```

Note: If the executable for the Naming Service is moved, it must be uninstalled and re-installed.

Any trace information provided by the service will be placed in the Windows Event Viewer with the title `NamingService`. To enable tracing information, add the desired trace configuration property (that is, the `ooc.naming.trace_level` property or one of the `ooc.orb.trace` properties) to the `HKEY_LOCAL_MACHINE` NT registry key with a `REG_SZ` value of at least 1.

Configuration Properties

In addition to the standard configuration properties described in [Chapter 4](#), Orbacus Names also supports the following properties:

<code>ooc.naming.callback_timeout=SECS</code>	Equivalent to the <code>-c</code> command-line option.
<code>ooc.naming.database=FILE</code>	Equivalent to the <code>-d</code> command-line option.
<code>ooc.naming.no_updates</code>	Equivalent to the <code>-n</code> command-line option.
<code>ooc.naming.endpoint=ENDPOINT</code>	Specifies the endpoint configuration for the service. Note that this property is only used if the <code>ooc.orb.oa.endpoint</code> property is not set.
<code>ooc.naming.timeout=MINS</code>	Equivalent to the <code>-t</code> command-line option.
<code>ooc.naming.trace_level=LEVEL</code>	Defines the output level for diagnostic messages printed by Orbacus Names. The default level is 0, which produces no output. A level of 1 or higher produces messages related to database operations, a level of 2 or higher produces messages related to adding and removing listeners, and a level of 3 or higher produces messages related to binding operations.

Persistence

Orbacus Names can optionally be used in a persistent mode, in which all data managed by the service is saved in a file. If you do not run the service in its persistent mode, all of the data will be lost when the service terminates.

It is also important to note that *when using the service in its persistent mode, you should always start the service on the same port* (see [Chapter 4](#) for more information).

Connecting to the Service

The object key of the Naming Service is `NameService`, which identifies an object of type `CosNaming::OBNamingContext`. The `OBNamingContext` interface is derived from the standard interface `CosNaming::NamingContextExt` and provides additional Orbacus-specific functionality. For a description of the `OBNamingContext` interface, please refer to the documented IDL file `naming/idl/OBNaming.idl`.

The object key can be used when composing URL-style object references. For example, the following URL identifies the naming service running on host `nshost` at port `10000`:

```
corbaloc::nshost:10000/NameService
```

Refer to [Chapter 6](#) for more information on URLs and configuring initial services.

Using the Naming Service with the IMR

The Naming Service may be used with the Implementation Repository (IMR). However, if used with the IMR, it is important to note that the `corbaloc` URL-style object reference described in the previous section cannot be used. If the IMR is used, then the object reference for the Naming Service must be created using one of the following methods (where `NamingServer` refers to the server name configured with the IMR):

- Start the Naming Service with the options:

```
--ior -ORBServerId NamingServer
```

causing the Naming Service to print its reference to standard output.

- Use the `mkref` utility:

```
mkref NamingServer NameService RootContextPOA
```

When using the Naming Service with the IMR, the service must be started with the option `-ORBServerId NamingServer`, where `NamingServer` refers to the server name configured with the IMR. When the IMR is configured to start the Naming Service, this option is automatically added to the service's arguments. However, when the Naming Service is started manually, the option must be present. For further information on configuring a service with the IMR, refer to [“Getting Started with the Implementation Repository” on page 195](#).

Bindings

Object references registered with the Naming Service are maintained in a hierarchical structure similar to a filesystem. A file in a filesystem is analogous to an object binding in the Naming Service. The equivalent for a folder in a filesystem is a naming context in Naming Service terms. The pieces of information stored in a Naming Service are called *bindings*. A binding consists of an object's name and its type, as defined in the CosNaming module:

```
// IDL
typedef string Istring;

struct NameComponent
{
    Istring id;
    Istring kind;
};

typedef sequence<NameComponent> Name;

enum BindingType
{
    nobject,
    ncontext
};

struct Binding
{
    Name binding_name;
    BindingType binding_type;
};
```

As you can see, each name consists of one or more components, like a file is fully specified by its path in a filesystem. Each name component consists of two strings, `id` and `kind`, which could be likened to a file's name and its extension. Generally, the filesystem analogy works very well when describing the Naming Service structures.

A new Naming Service entry (a binding) is created with the following operations:

```
// IDL
void bind(in Name n, in Object obj)
    raises(NotFound, CannotProceed, InvalidName, AlreadyBound);

void bind_context(in Name n, in NamingContext nc)
    raises(NotFound, CannotProceed, InvalidName, AlreadyBound);

NamingContext new_context();

NamingContext bind_new_context(in Name n)
    raises(NotFound, CannotProceed, InvalidName, AlreadyBound);
```

`bind` registers a new object with the Naming Service, whereas a new context is registered with `bind_context`. For each operation, an object reference and a `Name` are expected as parameters. New naming context objects are created with `new_context` or `bind_new_context`. `bind_context` and `bind_new_context` throw an `AlreadyBound` exception if the name is already in use in the target context.

To create a new binding without being concerned if the specified binding already exists, use the following operations:

```
// IDL
void rebind(in Name n, in Object obj)
    raises(NotFound, CannotProceed, InvalidName);

void rebind_context(in Name n, in NamingContext nc)
    raises(NotFound, CannotProceed, InvalidName);
```

Use the `unbind` operation to delete a particular binding:

```
// IDL
void unbind(in Name n)
    raises(NotFound, CannotProceed, InvalidName);
```

Name Resolution

Besides registering objects, an equally important task of the Naming Service is name resolution. A name is passed to the `resolve` or `resolve_str` operation and an object reference is returned if the name exists.

```
// IDL
Object resolve(in Name n)
raises(NotFound, CannotProceed, InvalidName);
Object resolve_str(in StringName n)
raises(NotFound, CannotProceed, InvalidName);
```

The `resolve` and `resolve_str` operations are only useful when a particular name is known in advance. Sometimes it is necessary to ask for a list of all bindings registered with a particular naming context. The `list` operation returns a list of bindings.

```
// IDL
typedef sequence<Binding> BindingList;

void list(in unsigned long how_many,
out BindingList bl, out BindingIterator bi);
```

If the number of bindings is especially large, the `BindingIterator` interface is provided so that you don't have to query for all available bindings at once. Simply get a certain number of bindings specified with `how_many`, and get the rest, if any, using the `BindingIterator`.

```
// IDL
interface BindingIterator
{
    boolean next_one(out Binding b);
    boolean next_n(in unsigned long how_many, out BindingList
bl);
    void destroy();
};
```

Make sure that you destroy the iterator object when it is no longer needed.

Programming Example

Orbacus includes simple C++ and Java examples that demonstrate how to use the CORBA Naming Service. These examples are located in the folder `naming/demo`. We will concentrate on the Java example, but the C++ example works similarly. The example expects a Naming Service server to be already running and that the server's initial reference can be resolved by the ORB. Because of its volume we have split the code into several parts for the discussion below.

Initialization

The first code fragment deals with initializing the ORB.

```
1 // Java
2 java.util.Properties props = System.getProperties();
3 props.put("org.omg.CORBA.ORBClass", "com.ooc.CORBA.ORB");
4 props.put("org.omg.CORBA.ORBSingletonClass",
5           "com.ooc.CORBA.ORBSingleton");
6
7 org.omg.CORBA.ORB orb = null;
8 try
9 {
10     orb = ORB.init(args, props);
11
12     org.omg.CORBA.Object poaObj = null;
13     try
14     {
15         poaObj = orb.resolve_initial_references("RootPOA");
16     }
17     catch(org.omg.CORBA.ORBPackage.InvalidName ex)
18     {
19         throw new RuntimeException();
20     }
21     POA rootPOA = POAHelper.narrow(poaObj);
22     POAManager manager = rootPOA.the_POAManager();
23
24     org.omg.CORBA.Object obj = null;
25     try
26     {
27         obj = orb.resolve_initial_references("NameService");
28     }
29     catch(org.omg.CORBA.ORBPackage.InvalidName ex)
30     {
31         throw new RuntimeException();
32     }
33
34     if(obj == null)
35     {
36         throw new RuntimeException();
37     }
```

```
38
39     NamingContextExt nc = null;
40     try
41     {
42         nc = NamingContextExtHelper.narrow(obj);
43     }
44     catch(org.omg.CORBA.BAD_PARAM ex)
45     {
46         throw new RuntimeException();
47     }
```

Lines 10-22 Usually the application is initialized in the `main` method. For more information on ORB initialization see [Chapter 4](#).

Lines 24-32 In the next step we try to connect to the Naming Service by supplying `NameService` to `resolve_initial_references`. If `InvalidName` is thrown, there is no Naming Service available because the ORB doesn't know anything about this service.

Lines 34-47 If calling `resolve_initial_references` was successful, the object reference is checked and narrowed in order to verify that it supports the interface `CosNaming::NamingContextExt`. If the `narrow` operation raises `CORBA::BAD_PARAM`, the object does not support the interface. This is considered to be an error because we explicitly asked for a Naming Service instance.

Binding

In the next step some sample bindings are created and bound to the Naming Service.

```
1 // Java
2   Named_impl implA = new Named_impl();
3   Named_impl implA1 = new Named_impl();
4   Named_impl implA2 = new Named_impl();
5   Named_impl implA3 = new Named_impl();
6   Named_impl implR = new Named_impl();
7   Named_impl implC = new Named_impl();
8   Named a = implA._this(orb);
9   Named a1 = implA1._this(orb);
10  Named a2 = implA2._this(orb);
11  Named a3 = implA3._this(orb);
12  Named b = implB._this(orb);
13  Named c = implC._this(orb);
14
15  try
16  {
17      NameComponent[] nc1Name = new NameComponent[1];
18      nc1Name[0] = new NameComponent();
19      nc1Name[0].id = "nc1";
20      nc1Name[0].kind = "";
21      NamingContext nc1 = nc.bind_new_context(nc1Name);
22
23      NameComponent[] nc2Name = new NameComponent[2];
24      nc2Name[0] = new NameComponent();
25      nc2Name[0].id = "nc1";
26      nc2Name[0].kind = "";
27      nc2Name[1] = new NameComponent();
28      nc2Name[1].id = "nc2";
29      nc2Name[1].kind = "";
30      NamingContext nc2 = nc.bind_new_context(nc2Name);
31
32      NameComponent[] aName = new NameComponent[1];
33      aName[0] = new NameComponent();
34      aName[0].id = "a";
35      aName[0].kind = "";
36      nc.bind(aName, a);
```

```

37
38     NameComponent[] a1Name = new NameComponent[1];
39     a1Name[0] = new NameComponent();
40     a1Name[0].id = "a1";
41     a1Name[0].kind = "";
42     nc.bind(a1Name, a1);
43
44     NameComponent[] a2Name = new NameComponent[1];
45     a2Name[0] = new NameComponent();
46     a2Name[0].id = "a2";
47     a2Name[0].kind = "";
48     nc.bind(a2Name, a2);
49
50     NameComponent[] a3Name = new NameComponent[1];
51     a3Name[0] = new NameComponent();
52     a3Name[0].id = "a3";
53     a3Name[0].kind = "";
54     nc.bind(a3Name, a3);
55
56     NameComponent[] bName = new NameComponent[2];
57     bName[0] = new NameComponent();
58     bName[0].id = "nc1";
59     bName[0].kind = "";
60     bName[1] = new NameComponent();
61     bName[1].id = "b";
62     bName[1].kind = "";
63     nc.bind(bName, b);
64
65     NameComponent[] cName = new NameComponent[3];
66     cName[0] = new NameComponent();
67     cName[0].id = "nc1";
68     cName[0].kind = "";
69     cName[1] = new NameComponent();
70     cName[1].id = "nc2";
71     cName[1].kind = "";
72     cName[2] = new NameComponent();
73     cName[2].id = "c";
74     cName[2].kind = "";
75     nc.bind(cName, c);
76 }

```

Lines 2-13 Several sample objects are created that will later be bound to our Naming Service. These objects implement an interface called `Named`. In this example, the details of this interface are not important. `Named` might even be an interface without any operations defined in it.

Lines 17-75 Create and bind some new contexts and bind the sample objects to these contexts. Each binding name consists of several `NameComponents` that are similar to the path components of a file located somewhere in a filesystem. Objects are bound with the Naming Service's `bind` operation; for contexts, the corresponding operation `bind_context` is used. In addition to the object's IOR, both operations expect a unique binding name. If a name already exists, an `AlreadyBound` exception is thrown. There are also other exceptions you might encounter at this stage, for example, `IllegalName` if an empty string was provided as part of a `NameComponent`.

Exceptions

This code fragment deals with exceptions that may be thrown by the Naming Service operations.

```
// Java
catch(NotFound ex)
{
    System.err.print("Got a 'NotFound' exception (");
    switch(ex.why.value())
    {
        case NotFoundReason._missing_node:
            System.err.print("missing node");
            break;

        case NotFoundReason._not_context:
            System.err.print("not context");
            break;

        case NotFoundReason._not_object:
            System.err.print("not object");
            break;
    }

    System.err.println(")");
    ex.printStackTrace();
    throw new SystemException();
}
catch(CannotProceed ex)
{
    System.err.println("Got a 'CannotProceed' exception");
    ex.printStackTrace();
    throw new SystemException();
}
catch(InvalidName ex)
{
    System.err.println("Got an 'InvalidName' exception");
    ex.printStackTrace();
    throw new SystemException();
}
```

```
catch(AlreadyBound ex)
{
    System.err.println("Got an 'AlreadyBound' exception");
    ex.printStackTrace();
    throw new SystemException();
}
```

Catch exceptions. Don't ever forget to do this. It can be useful to call `printStackTrace` on the exception object in order to get detailed information about the program flow causing the exception.

The Event Loop

Next we start listening for requests.

```
// Java
try
{
    manager.activate();
}
catch(org.omg.PortableServer.POAManagerPackage.AdapterInactive
ex)
{
    throw new RuntimeException();
}
orb.run();
```

Everything is ready now, so we can listen for requests by calling `actiavate` on the POA Manager and `run` on the ORB.

Releasing Resources

Some cleanup work should be done before exiting the program. Every binding must be properly unbound and the ORB must be destroyed.

```
1 // Java
2     nc.unbind(cName);
3     nc.unbind(bName);
4     nc.unbind(aName);
5     nc.unbind(a1Name);
6     nc.unbind(a2Name);
7     nc.unbind(a3Name);
8     nc.unbind(nc2Name);
9     nc.unbind(nc1Name);
10 }
11 catch(RuntimeException ex)
12 {
13     status = 1;
14 }
15
16 if (orb != null)
17 {
18     try
19     {
20         orb.destroy();
21     }
22     catch(const RuntimeException ex)
23     {
24         status = 1;
25     }
26 }
27
28 System.exit(status);
```

Lines 2-9 All bindings are unbound.

Lines 16-26 `destroy` is called on the ORB. This releases the resources used by the ORB.

The complete example can be found in the folder `naming/demo` included with the Orbacus distribution.

Orbacus Names Console

Orbacus Names includes a graphical client for administering the service called the Orbacus Names Console. The application can manage any CORBA-compliant Naming Service, but additional features are provided when used with Orbacus Names.

In this chapter

This chapter contains the following sections:

Usage	page 234
Naming Service Lookup	page 235
The Menus	page 236
The Toolbar	page 244
The Popup Menu	page 245

Usage

Syntax

Use the Orbacus Names Console as follows:

```
com.ooc.CosNamingConsole.Main
  [-f,--file FILE] [-i,--ior] [-n,--no-updates] [--look CLASS]
  [--windows] [--motif] [--mac] [-h,--help] [-v, --version]
```

-f FILE --file FILE	Read the Naming Service IOR from FILE.
-i --ior	Print the stringified IOR of the Naming Service to standard output.
-n --no-updates	Disables automatic updates. That is, callbacks that notify interested clients of changes to the naming service.
--look CLASS	Use the specified Look & Feel class.
--windows	Use the Windows Look & Feel (if available).
--motif	Use the Motif Look & Feel (if available).
--mac	Use the Macintosh Look & Feel (if available).
-h --help	Display the command-line options supported by the program.

CLASSPATH Requirements

The Orbacus Names Console requires the classes in `OB.jar`, `OBNaming.jar` and `OBUtil.jar`.

Naming Service Lookup

In order to locate a Naming Service, the application takes the following steps on start-up:

- First it checks whether a Naming Service reference was given with the -f option.
- If this is not the case, then the initial Naming Service is used, as provided to the ORB with options like -ORBservice or -ORBconfig.

If both of the above steps fail, an error window is displayed and the Names console exits.

The Menus

The menus provide access to all of the features of the application. In addition, the most common actions are also available in the toolbar, as well as in a popup menu that is displayed when pressing the right mouse button over an item in the binding table or context tree.

The File Menu


This menu contains operations that create bindings and define the current root context.

New Window	Opens an additional control window.
Switch Root Context	Selects a new root naming context.
Load Context	Recursively loads a naming context from a file.
Save Context As	Recursively saves the selected naming context to a file.
Save IOR to File	Saves the stringified IOR of the currently selected item to a file.
Close Window	Closes the current window.
Exit	Quits the Orbacus Names Console.

After starting the application, the current root context is the naming context corresponding to the IOR specified on the command line or the initial Naming Service, as provided to the ORB with options like `-ORBservice` or

-ORBconfigby. You can make another naming context the root context using **Switch Root Context**. The new root context's IOR is specified in the **Enter IOR** dialog window, as shown in [Figure 5](#).

Figure 5: *Entering an IOR*



The IOR can be entered directly or can be read from a file. If an IOR is entered manually you usually either use the URL-style notation as described in [Chapter 6 on page 147](#), or you copy a stringified object reference into the dialog box using copy and paste. After selecting **Browse** a file containing an IOR can be selected.

Sometimes it is not desirable to completely replace the currently visible root context by another root context. For example, you may need to copy bindings from one context to another. If this is the case, simply open an additional window for the new root context using **New Window**. You can then switch the root context in only one window without affecting the information displayed in the other one. Using two windows, you can easily transfer bindings from one context to another using copy and paste.

Complete naming contexts can be loaded from a special file with naming context information. Such a file, which was previously created with **Save Context As**, is loaded with **Load Context**. The bindings saved to this file are added to the current naming context.

When saving a naming context, the console checks each context for accessibility. If a context cannot be accessed — that is, if its contents cannot be saved — a message is displayed in the error window. You also get an error message if the console detects a recursion. The bindings contained in the naming context leading to the recursion is not saved.

Use **Save IOR to File** in order to create a file that contains the stringified IOR of the currently selected binding or context.

With **Close Window** the current window is closed. Closing the last window causes the application to terminate. **Exit** can be used to terminate the application regardless of how many windows are open.

The Edit Menu

The operations in this menu provide the means for creating and deleting objects and for changing the Naming Service structure.

New Context	Creates a new naming context.
New Binding	Creates a new binding for an object.
Delete	Deletes the selected items.
Link	Creates a new binding for an existing naming context.
Unlink	Unbinds the selected items.
Cut	Moves the selected items to the clipboard.
Copy	Copies the selected items to the clipboard.
Paste	Inserts the clipboard contents.
Change ID	Edits the ID field of the selected item.
Change Kind	Edits the Kind field of the selected item.
Change IOR	Edits the IOR of the selected item.
Select all	Selects all items in the object table.
Invert Selection	Inverts the current selection.

New contexts and bindings are created with the operations **New Context** and **New Binding**, respectively. If one of these functions is selected, a new context or object binding with a unique name is added to the current context. For new object bindings an IOR can be specified.

Use **Delete** to remove the selected items from a naming context. Deleting Naming Service entries removes all selected bindings from their parent context. The objects belonging to these bindings are not affected. Destroying Naming Service information only affects the actual Naming Service data, not the objects themselves.

Use **Link** to create a new binding for an existing naming context, where the naming context is specified by an IOR. The operation **Unlink** unbinds the selected items. For objects, **Unlink** is equivalent to **Delete**, but for contexts, **Unlink** differs in that the context is not destroyed. Since a context is not destroyed using Unlink, it should only be used when there are multiple bindings to a context in order to avoid orphaned contexts.

The console supports a clipboard that you can use to move bindings between different contexts. Data is transferred to the clipboard using the **Cut** or **Copy** commands. **Cut** moves the currently selected items to the clipboard and deletes the original entries, whereas **Copy** simply creates a copy in the clipboard but keeps the source entry unchanged. When new data is transferred to the clipboard, the old clipboard contents are replaced. Using **Paste**, you can add the clipboard data into a naming context. The clipboard contents are not changed by this operation. That is, you can **Paste** the same items several times. Note that if naming contexts are transferred to the clipboard, their contents are not evaluated before they are pasted. It is during the **Paste** operation that the bindings of a context are duplicated. This means that if new bindings are added to a context after a **Cut** or **Copy** operation, these bindings will be present after pasting this context.

An item registered with the Naming Service has three modifiable attributes: its ID, its Kind and its IOR. The ID and Kind attributes can be edited by simply double-clicking the **ID** or **Kind** field in the table. You can also change binding attributes with the corresponding menu operations **Change ID**, **Change Kind** and **Change IOR**. Entering a new IOR for an existing name effectively replaces an object registered with the Naming Service by another object with the same name.

Use **Select all** to select all of the entries in the binding table. The current table selection can be inverted using **Invert Selection**.

The View Menu

The operations in this menu control the appearance of the console window as well as the presentation of the Naming Service data.

Toolbar	Toggles the toolbar visibility.
Status Bar	Toggles the statusbar visibility.
Error Window	Toggles the error message window visibility.
Simple List	Displays minimum object information.
Details	Displays additional object information.
Sort	Sets sorting mode for object list.
Refresh	Updates the complete window contents

A toolbar that gives access to frequently needed operations is normally present below the menu. If you don't have a need for this toolbar or if you just want to save space on the screen, you can switch it off with the **Toolbar** toggle button. The same applies to the status bar where information about the currently selected item is displayed. The status bar displays an object's repository ID, the host where this object is located and the port it is bound to. If an item with a nil object reference is selected or if multiple items are selected, the status bar is empty.

If an error occurs while editing bindings, the console automatically displays a new window with information about what went wrong. Usually this information consists of exception data. The visibility of this window can be explicitly controlled with the **Error Window** toggle button.

If the console is connected to Orbacus Names, as described in [Chapter 9](#), the console can display timestamp information for each binding by making use of proprietary features of Orbacus Names. This information is shown in the binding table if the **Details** display mode instead of the **Simple List** mode is active.

Usually the console sorts the items in the binding table in ascending alphabetical order, with naming contexts being listed at the top. You can change this order with the options available in the **Sort** menu. Bindings can be sorted by their ID or Kind fields. If the extended attributes are displayed, items can also be sorted by date and time. You can reverse the sort order by

selecting the current sorting mode a second time in the **View** menu or by clicking on the table header cells. In this case, the display switches from ascending to descending order and vice versa.

If the contents of a naming context have been changed by a third party and you want to update the information displayed in the console window, selecting **Refresh** updates the display. If the console is connected to Orbacus Names, a refresh is done automatically each time a change occurs.


The Tools Menu

The operations available in this menu are meant as tools for your everyday work.

- Ping** Checks the accessibility of the selected items.
- Clean up Unbinds inaccessible objects from the current context.

Sometimes it is useful to check if an object bound to a name still exists or if the object reference associated with it has become invalid, for example, because of a server crash. To perform such a check, select all the objects you want to check and start the **Ping** operation. The console tries to contact each of the selected objects and displays the time it took to get a connection to them in a separate window.

Figure 6: *The Ping Window*



This is very similar to the Windows or Unix `ping` command for an IP address or a host name. If there is a time-out while trying to contact an object, this information is displayed in the Ping Window and the console continues with the next object.

If you want objects that cannot be contacted, for example because of a server breakdown, to be unbound from the current context, **Clean up** does the job. **Clean up** non-recursively tries to connect to the selected objects. If there is a communication failure or the `_non_existent()` operation returns true for a particular object, the corresponding binding is automatically removed. **Clean up** should be used with care.

The Toolbar

In addition to the operations offered by the menu bar, some frequently needed functions are available by icons located in the toolbar, as shown in [Figure 7](#).

Figure 7: *A closer look at the toolbar*



The icon on the toolbar's left is the **Upwards** icon which changes the naming context to the parent of the context currently being displayed. The next five icons correspond to the **New Context**, **New Binding**, **Cut**, **Copy**, **Paste** and **Delete** items as described in [“The Edit Menu” on page 238](#).

The **Simple List** and **Details** items from the **View** menu are the next two icons in the toolbar. They determine whether the binding table displays only the ID and Kind fields, or, if Orbacus Names is available, also the date and time the binding was last modified.

The last item in the menubar corresponds to the **Refresh** operation from the **View** menu.

The Popup Menu

When selecting an item in the binding table or a tree node with the right mouse button, a popup menu with a choice of operations is displayed as shown in [Figure 8](#).

Figure 8: *A popup menu offers important operations*



This is another convenient alternative for executing frequently used operations.

Orbacus Properties

*The CORBA Property Service permits you to annotate an object with extra attributes (called *properties*) that were not defined by the object's IDL interface. Properties can represent any value because they make use of the CORBA `Any` data type.*

Orbacus Properties is compliant with [10]. This chapter does not provide a complete description of the service. It only provides an overview, suitable to get you started. For more information, please refer to the specification.

In this chapter

This chapter contains the following sections:

Usage	page 248
Connecting to the Service	page 250
Using the Property Service with the IMR	page 251
Creating Properties	page 252
Querying for Properties	page 253
Deleting Properties	page 255
Programming Example	page 256

Usage

Orbacus includes functionally equivalent implementations of the Property Service in C++ and Java.

Note: The Property Service has nothing to do with the properties used for configuration purposes. Configuration properties are described in [“ORB Properties” on page 78](#).

Syntax

For C++:

```
probserv
  [-h,--help] [-v,--version] [-i,--ior]
```

For Java:

```
om.ooc.CosPropertyService.Server
  [-h,--help] [-v,--version] [-i,--ior]
```

Options

The options in the following table apply to both C++ and Java versions.

-h --help	Display the command-line options supported by the server.
-v --version	Display the version of the server.
-i --ior	Prints the stringified IOR of the server to standard output.

Configuration Properties

In addition to the standard configuration properties described in [Chapter 4](#), Orbacus Properties also supports the following properties:

<code>ooc.property.endpoint=ENDPOINT</code>	Specifies the endpoint configuration for the service. Note that this property is only used if the <code>ooc.orb.oa.endpoint</code> property is not set.
---	---

CLASSPATH Requirements

Orbacus Properties for Java requires the classes in `OB.jar` and `OBProperty.jar`.

Connecting to the Service

The object key of the Property Service is `PropertyService`, which identifies an object of type `CosPropertyService::PropertySetDefFactory`.

The object key can be used when composing URL-style object references. For example, the following URL identifies the Property Service running on host `prophost` at port `10000`:

```
corbaloc::prophost:10000/PropertyService
```

Refer to [Chapter 6](#) for more information on URLs and configuring initial services.

Using the Property Service with the IMR

The Property Service may be used with the Implementation Repository (IMR). However, if used with the IMR, it is important to note that the corbaloc URL-style object reference described in the previous section cannot be used. If the IMR is used, then the object reference for the Property Service must be created using one of the following methods (where `PropertyServer` refers to the server name configured with the IMR):

- Start the Property Service with the options:

```
--ior -ORBServerId PropertyServer
```

causing the Property Service to print its reference to standard output.

- Use the `mkref` utility:

```
mkref PropertyServer PropertyService PropertyServicePOA
```

When using the Property Service with the IMR, the service must be started with the option `-ORBServerId PropertyServer`, where `PropertyServer` refers to the server name configured with the IMR. When the IMR is configured to start the Property Service, this option is automatically added to the service's arguments. However, when the Property Service is started manually, the option must be present. For further information on configuring a service with the IMR, refer to [“Getting Started with the Implementation Repository” on page 195](#).

Creating Properties

A property handled by the CORBA Property Service consists of two components: the property's name and its value. The name is a CORBA `string` and the associated value is represented by a CORBA `Any`:

```
// IDL
typedef string PropertyName;

struct Property
{
    PropertyName property_name;
    any property_value;
};
```

New properties are created using a factory object implementing the `PropertySet` interface. A new property is created using the `define_property` operation:

```
// IDL
void define_property(in PropertyName, in any property_value)
    raises(InvalidPropertyName, ConflictingProperty,
          UnsupportedTypeCode, UnsupportedProperty, ReadOnlyProperty);
```

As a property consists of a name–value pair, both the name and the value are the parameters to this operation.

Querying for Properties

As soon as a property is defined, the `PropertySet` can be queried for the property's value with the `get_property_value` operation:

```
// IDL
any get_property_value(in PropertyName property_name)
    raises(PropertyNotFound, InvalidPropertyName);
```

For a particular property name, this call either returns the `Any` associated with that name or throws an exception if a property with the name does not exist.

You can not only query for a particular property value, but also for a list of all the properties defined within a `PropertySet`. The `get_all_properties` operation serves this purpose:

```
// IDL
void get_all_properties(in unsigned long how_many,
    out Properties nproperties, out PropertiesIterator rest);
```

This operation works similar to the `list` call offered by the Naming Service. In both cases the maximum number of items to be returned at once is specified. An iterator implementing the `PropertiesIterator` interface gives access to the remaining items, if any.

```
// IDL
interface PropertiesIterator
{
    void reset();

    boolean next_one(out Property aproperty);

    boolean next_n(in unsigned long how_many,
out Properties nproperties);

    void destroy();
};
```

If you are only interested in a list of property names you can get this list by calling `get_all_property_names`:

```
// IDL
void get_all_property_names(in unsigned long how_many,
    out PropertyNames property_names,
    out PropertyNamesIterator rest);
```

As with `get_all_properties` a list of names as well as an iterator is returned. This iterator implements the `PropertyNamesIterator` interface:

```
// IDL
interface PropertyNamesIterator
{
    void reset();

    boolean next_one(out PropertyName property_name);

    boolean next_n(in unsigned long how_many,
        out PropertyNames property_names);

    void destroy();
};
```

The iterators should always be destroyed when they are no longer needed. Sometimes it is useful to know of how many properties a `PropertySet` consists of. This information is provided by `get_number_of_properties`:

```
// IDL
unsigned long get_number_of_properties();
```

Note that you have to be careful if you intend to use the return value of `get_number_of_properties` as the input value for the `how_many` parameter of `get_all_properties` in order to get a complete property list. You always have to check the `PropertiesIterator` for properties that were not returned as part of the `Properties` sequence returned by `get_all_properties`, otherwise you might miss a property that was defined by another process between your calls to `get_number_of_properties` and `get_all_properties`.

Deleting Properties

If a property has become obsolete it can be deleted from the `PropertySet` with `delete_property`:

```
// IDL
void delete_property(in PropertyName property_name)
raises(PropertyNotFound, InvalidProperty, FixedProperty);
```

As you might have guessed by this operation's signature, there are properties that cannot be deleted at all. This kind of property is called a `FixedProperty`. The Property Service defines several other special property types, such as read-only properties. Please refer to the [OMG Property Service \[9\]](#) specification for details.

Programming Example

The Property Service test suite, which is part of the Orbacus distribution, provides a good example of how to create properties and query for their values. The code below is based on excerpts of this test suite, which is located in the directory `property/test`. We will concentrate on an example in Java here. As with the previous examples, the Java code is very similar to what is necessary in C++. The example demonstrates how to create properties and how to get a list of all the properties defined within a `PropertySet`.

```
1 // Java
2
3 org.omg.CORBA.Object obj = null;
4
5 try
6 {
7     obj = orb.resolve_initial_references("PropertyService");
8 }
9 catch(org.omg.CORBA.ORBPackage.InvalidName ex)
10 {
11     // An error occurred, Property Service is not available
12 }
13
14 if(obj == null)
15 {
16     // The object reference is invalid
17 }
18
19 PropertySetDefFactory factory = null;
20 try
21 {
22     factory = PropertySetDefFactoryHelper.narrow(obj);
23 }
24 catch(org.omg.CORBA.BAD_PARAM ex)
25 {
26     // This object does not implement the Property Service
27 }
28
29 PropertySetDef set = factory.create_propertysetdef();
30
```



```

31 Any anyLong = orb.create_any();
32 Any AnyString = orb.create_any();
33 Any anyShort = orb.create_any();
34 anyLong.insert_long(12345L);
35 anyString.insert_string("Foo");
36 anyShort.insert_short((short)0);
37
38 try
39 {
40     set.define_property("LongProperty", anyLong);
41     set.define_property("StringProperty", anyString);
42     set.define_property("ShortProperty", anyShort);
43 }
44 catch(ReadOnlyProperty ex)
45 {
46     // An error occurred
47 }
48 catch(ConflictingProperty ex)
49 {
50     // An error occurred
51 }
52 catch(UnsupportedProperty ex)
53 {
54     // An error occurred
55 }
56 catch(UnsupportedTypeCode ex)
57 {
58     // An error occurred
59 }
60 catch(InvalidPropertyName ex)
61 {
62     // An error occurred
63 }
64
65 PropertiesHolder ph = new PropertiesHolder();
66 PropertiesIteratorHolder ih = new PropertiesIteratorHolder();
67 set.get_all_properties(0, ph, ih);
68
69 PropertyHolder h = new PropertyHolder();
70 while(ih.value.next_one(h))
71 {
72     // The next property is now stored in h.value
73
74 ih.value.destroy();

```

Lines 5-27 Get a Property Service reference and check for errors.

Line 29 The `PropertySetDefFactory` object is used to create a `PropertySetDef` instance. Note that `PropertySetDef` is a subclass of `PropertySet`.

Lines 31-36 Each property consists of a name and a value in the form of a CORBA `Any`.

Lines 38-63 Three properties are defined. The first has the name `LongProperty` and stores a `long` value. The second one is called `StringProperty` and stores a `string`. The remaining property represents a `short` value. If for some reason a property cannot be created, an exception is thrown.

Lines 65-73 Now we try to get a list of all the properties that were previously defined. With `get_all_properties` the `PropertySetDef` returns its properties. As we have set the `how_many` parameter to 0, we have to use the `PropertiesIterator` for each item. An application would normally provide a positive integer for `how_many`.

Line 74 The iterator has fulfilled its duty and can now be destroyed.

Orbacus Events

Some applications need to exchange information without explicitly knowing about each other. Often a server isn't even aware of the nature and number of clients that are interested in the data the server has to offer. A special mechanism is required that provides decoupled data transfer between servers and clients. This requirement is addressed by the CORBA Event Service.

Orbacus Events is compliant with [9]. This chapter does not provide a complete description of the service. It only provides an overview, suitable to get you started. For more information, please refer to the specification.

In this chapter

This chapter contains the following sections:

Usage	page 260
Connecting to the Service	page 265
Using the Event Service with the IMR	page 266
Event Service Concepts	page 267
Programming Example	page 275

Usage

Orbacus includes functionally equivalent implementations of the Event Service in C++:

```
eventserv
  [-h,--help] [-v,--version] [-i,--ior] [-t,--typed-service]
  [-u,--untyped-service]
```

and Java:

```
com.ooc.CosEvent.Server
  [-h,--help] [-v,--version] [-i,--ior] [-t,--typed-service]
  [-u,--untyped-service]
```

Options

The options in the following table apply to both C++ and Java versions.

-h	Display the command-line options supported by the server.
--help	
-v	Display the version of the server.
--version	
-i	Print the stringified IOR of the server to standard output.
--ior	
-t	Run a typed event service.
--typed-service	
-u	Run an untyped event service. This is the default behavior.
--untyped-service	

Windows Native Service

The C++ version of Orbacus Events is also available as a native Windows service.

```
nteventservice
  [-h,--help] [-i,--install] [-s,--start-install]
  [-u,--uninstall] [-d,--debug]
```

-h	Display the command-line options supported by the server.
--help	
-i	Install the service. The service must be started manually.
--install	
-s	Install and start the service.
--start-install	
-u	Uninstall the service.
--uninstall	
-d	Run the service in debug mode.
--debug	

In order to use the Event Service as a native Windows service, it is first necessary to add the `ooc.event.endpoint` property to the `HKEY_LOCAL_MACHINE` NT registry key (see [“Using the Windows Registry”](#) on [page 91](#) for more details).

Next the service should be installed with:

```
nteventservice -i
```

This adds the Orbacus Event Service entry to the Services dialog in the Control Panel. To start the event service, select the Orbacus Event Service entry, and press Start. If the service is to be started automatically when the machine is booted, select the Orbacus Event Service entry, then click Startup. Next select Startup Type - Automatic, and press OK. Alternatively, the service could have been installed using the `-s` option, which configures the service for automatic start-up:

```
nteventservice -s
```

If you want to remove the service, run:

```
ntrac -u
```

Note: If the executable for the Event Service is moved, it must be uninstalled and re-installed.

Any trace information provided by the service is placed in the Windows Event Viewer with the title `EventService`. To enable tracing information, add the desired trace configuration property (that is, one of the `ooc.event.trace` properties or one of the `ooc.orb.trace` properties) to the `HKEY_LOCAL_MACHINE` NT registry key with a `REG_SZ` value of at least 1.

Configuration Properties

In addition to the standard configuration properties described in [Chapter 4](#), Orbacus Events also supports the following properties:

<code>ooc.event.inactivity_timeout=SEC</code>	Proxies that are inactive for the specified number of seconds will be reaped. The default value is four hours.
<code>ooc.event.max_events=N</code>	The maximum number of events in each event queue. If this limit is reached and another event is received, the oldest event is discarded. The default value is 10.
<code>ooc.event.max_retries=N</code>	The maximum number of times to retry before giving up and disconnecting the proxy. The default value is 10.
<code>ooc.event.endpoint=ENDPOINT</code>	Specifies the endpoint configuration for the service. Note that this property is only used if the <code>ooc.orb.oa.endpoint</code> property is not set.
<code>ooc.event.pull_interval=MSEC</code>	This specifies the number of milliseconds between successive calls to pull on <code>PullSupplier</code> . Default value is 0.
<code>ooc.event.reap_frequency=SEC</code>	This specifies the frequency (in seconds) in which inactive proxies will be reaped. The default value is thirty minutes. Setting this property to 0 disables the reaping of proxies.
<code>ooc.event.retry_timeout=MSEC</code>	Specifies the initial amount of time in milliseconds that the service waits between successive retries. The default value is 1000.
<code>ooc.event.retry_multiplier=N</code>	A <code>double</code> that defines the factor by which the <code>retry_timeout</code> property should be multiplied for each successive retry.

<code>ooc.event.request_timeout=MSEC</code>	The amount of time permitted for a blocking request on a client to return before a timeout. The default value is 5 seconds.
<code>ooc.event.trace.events=LEVEL</code>	Defines the output level for event diagnostic messages printed by Orbacus Events. The default level is 0, which produces no output. A level of 1 or higher produces event processing information and a level of 2 or higher produces event creation and destruction information.
<code>ooc.event.trace.lifecycle=LEVEL</code>	Defines the output level for lifecycle diagnostic messages printed by Orbacus Events. The default level is 0, which produces no output. A level of 1 or higher produces lifecycle information (for example, creation and destruction of Suppliers and Consumers).
<code>ooc.event.typed_service=true false</code>	Equivalent to the <code>-t</code> command-line option.

CLASSPATH Requirements

Orbacus Events for Java requires the classes in `OB.jar` and `OBEvent.jar`.

Connecting to the Service

The object key of the Event Service depends on whether it is running as a typed or untyped service. The object keys and corresponding interface types are shown in [Table 2](#).

Table 2: *Object Keys and Interface Types*

	Object Key	Interface Type
Event Service	DefaultEventChannel	CosEventChannelAdmin::EventChannel
Typed Event Service	DefaultTypedEventChannel	CosTypedEventChannelAdmin::TypedEventChannel

The object key can be used when composing URL-style object references. For example, the following URL identifies the untyped event service running on host `evhost` at port 10000:

```
corbaloc::evhost:10000/DefaultEventChannel
```

Refer to [Chapter 6](#) for more information on URLs and configuring initial services.

Orbacus Events also provides proprietary factory interfaces which allow construction and administration of multiple event channels in a single service. The object keys and corresponding interface types of the factories are shown in [Table 3](#).

Table 3: *Object Keys and Interface Types for Event Channel Factories*

	Object Key	Interface Type
Event Channel Factory	DefaultEventChannelFactory	OBEventChannelFactory::EventChannelFactory
Typed Event Channel Factory	DefaultTypedEventChannelFactory	OBTypedEventChannelFactory::TypedEventChannelFactory

For a description of the factory interfaces, please refer to the documented IDL files `event/idl/OBEventChannelFactory.idl` and `event/idl/OBTypedEventChannelFactory.idl`.

Using the Event Service with the IMR

The Event Service may be used with the Implementation Repository (IMR). However, if used with the IMR, it is important to note that the `corbaloc` URL-style object reference described in the previous section cannot be used. If the IMR is used, then the object reference for the untyped Event Service must be created using one of the following methods (where `EventServer` refers to the server name configured with the IMR):

- Start the Event Service with the options:

```
-ORBServerId EventServer --ior
```

causing the Event Service to print its reference to standard output.
- Use the `mkref` utility:

```
mkref EventServer DefaultEventChannel EventServicePOA
```

For the typed Event Service, the object reference must be created using one of the following methods:

- Start the Event Service with the options:

```
-ORBServerId EventServer --typed-service --ior
```

causing the Event Service to print its reference to standard output.
- Use the `mkref` utility:

```
mkref EventServer DefaultTypedEventChannel EventServicePOA
```

Object references for the Orbacus proprietary factory objects can be created using the following commands:

```
mkref EventServer DefaultEventChannelFactory EventServicePOA
mkref EventServer DefaultTypedEventChannelFactory
EventServicePOA
```

When using the Event Service with the IMR, the service must be started with the option `-ORBServerId EventServer`, where `EventServer` refers to the server name configured with the IMR. When the IMR is configured to start the Event Service, this option is automatically added to the service's arguments. However, when the Event Service is started manually, the option must be present. For further information on configuring a service with the IMR, refer to [“Getting Started with the Implementation Repository” on page 195](#).

Event Service Concepts

In this section

This section contains the following topics:

The Event Channel	page 268
Event Suppliers and Consumers	page 269
Event Channel Policies	page 271
Event Channel Factories	page 272

The Event Channel

The Event Service distributes data in the form of events. The term *event* in this context refers to a piece of information that is contributed by an event source. An event channel instance accepts this information and distributes it to a list of objects that previously have connected to the channel and are listening for events.

The Event Service specification defines two distinct kinds of event channels: untyped and typed. Whereas an untyped event channel forwards every event to each of the registered clients in the form of a CORBA `Any`, a typed event channel works more selectively by supporting strongly-typed events which allow for data filtering. We will only discuss the untyped event channel here. For information on typed event channels, and more details on the Event Service in general, please refer to the official Event Service specification [\[9\]](#).

Event Suppliers and Consumers

Applications participating in generating and accepting events are called *suppliers* and *consumers*, respectively. Suppliers and consumers each come in two different versions, namely, *push suppliers* and *pull suppliers*, and *push consumers* and *pull consumers*.

What's the difference between pushing events and pulling events? Let's have a look at the consumer side first. Some consumers must be immediately informed when new events become available on an event channel. Such consumers usually act as push consumers. They implement the `PushConsumer` interface which ensures that the event channel actively forwards events to them using the `push()` operation:.

```
// IDL
interface PushConsumer
{
    void push(in any data)
        raises(Disconnected);

    void disconnect_push_consumer();
};
```

Push consumers are passive, that is, are servers. Conversely, pull consumers are active, that is, are clients. Pull consumers poll an event channel for new events. As events may arrive at a greater rate than they are polled for by a pull consumer or accepted and processed by a push consumer, some events might get lost. A buffering policy implemented by the event channel determines whether events are buffered and what happens in case of an event queue overflow.

Like consumers, suppliers can also use push or pull behavior. Push suppliers are the more common type, in which the supplier directly forwards data to the event channel and thus plays the client role in the link to the channel. Pull suppliers, on the other hand, are polled by the event channel and supply an event in response, if a new event is available. Polling is done by the `try_pull()` operation if it is to be non-blocking or by the blocking `pull()` call:

```
// IDL
interface PullSupplier
{
    any pull()
        raises(Disconnected);

    any try_pull(out boolean has_event)
        raises(Disconnected);

    void disconnect_pull_supplier();
};
```

Event Channel Policies

The untyped event channel implementation included in the Orbacus distribution features a simple event queue policy. Events are buffered in the form of a queue: a certain number of events are stored and, in case of a buffer overflow, the oldest events are discarded.

Event Channel Factories

The standard CORBA Event Service provides no support for managing the lifecycle of event channels; as a result, applications requiring multiple channels are often forced to run a separate instance of the Event Service for each channel. To remedy this situation, Orbacus Events provides optional, proprietary interfaces for event channel administration.

The `OBEventChannelFactory::EventChannelFactory` interface describes the factory for untyped event channels:

```
// IDL
module OBEventChannelFactory
{
    typedef string ChannelId;
    typedef sequence<ChannelId> ChannelIdSeq;

    exception ChannelAlreadyExists {};
    exception ChannelNotAvailable {};

    interface EventChannelFactory
    {
        CosEventChannelAdmin::EventChannel
        create_channel(in ChannelId id)
            raises (ChannelAlreadyExists);

        CosEventChannelAdmin::EventChannel
        get_channel_by_id(in ChannelId id)
            raises (ChannelNotAvailable);

        ChannelIdSeq get_channels();

        void shutdown();
    };
};
```


The `OBTypedEventChannelFactory::TypedEventChannelFactory` interface describes the factory for typed event channels:

```
// IDL
module OBTypedEventChannelFactory
{
  interface TypedEventChannelFactory
  {
    CosTypedEventChannelAdmin::TypedEventChannel
    create_channel(in OBEventChannelFactory::ChannelId id)
      raises(OBEventChannelFactory::ChannelAlreadyExists);

    CosTypedEventChannelAdmin::TypedEventChannel
    get_channel_by_id(in OBEventChannelFactory::ChannelId id)
      raises(OBEventChannelFactory::ChannelNotAvailable);

    OBEventChannelFactory::ChannelIdSeq get_channels();

    void shutdown();
  };
};
```

At start-up, the untyped Event Service creates a single channel having the identifier `DefaultEventChannel`, and the typed Event Service creates a single channel having the identifier `DefaultTypedEventChannel`. A channel's identifier also serves as its object key; therefore, a channel can be located using a `corbaloc: URL` (see “[corbaloc: URLs](#)” on page 161). For example, a channel with the identifier `TelemetryData` can be located on the host `myhost` at port 2098 using the following URL:

```
corbaloc::myhost:2098/TelemetryData
```

To obtain the object reference of a channel factory, use a `corbaloc: URL` with the object key as shown in [Table 2 on page 265](#). For example, assuming the untyped Event Service is running on host `myhost` at port 2098, here is how a C++ application can obtain the object reference of the channel factory and create a channel with the identifier `TelemetryData`:

```
// C++
CORBA::Object_var obj = orb -> string_to_object(
  "corbaloc::myhost:2098/DefaultEventChannelFactory");
OBEventChannelFactory::EventChannelFactory_var factory =
  OBEventChannelFactory::EventChannelFactory::_narrow(obj);
CosEventChannelAdmin::EventChannel_var channel =
  factory -> create_channel("TelemetryData");
```

Here is the same example in Java:

```
// Java
org.omg.CORBA.Object obj = orb.string_to_object(
    "corbaloc::myhost:2098/DefaultEventChannelFactory");
com.ooc.OBEventChannelFactory.EventChannelFactory factory =
    com.ooc.OBEventChannelFactory.EventChannelFactoryHelper.
    narrow(obj);
org.omg.CosEventChannelAdmin.EventChannel channel =
    factory.create_channel("TelemetryData");
```

Programming Example

In the Event Service example that comes with Orbacus, two supplier and two consumer clients demonstrate how to use an untyped event channel to propagate information. The pieces of information transferred by this example are strings containing the current date and time. After starting the Event Service server, you can start these clients in any order. The demo applications obtain the initial Event Service reference as already demonstrated, by calling `resolve_initial_references`. When started, each supplier provides information about the current date and time and each client displays the event data in its console window.

This is the push supplier's main loop:

```
1 // Java
2 while (consumer_ != null)
3 {
4     java.util.Date date = new java.util.Date();
5     String s = "PushSupplier says: " + date.toString();
6
7     Any any = orb_.create_any();
8     any.insert_string(s);
9
10    try
11    {
12        consumer_.push(any);
13    }
14    catch (Disconnected ex)
15    {
16        // Supplier was disconnected from event channel
17    }
18
19    try
20    {
21        Thread.sleep(1000);
22    }
23    catch (InterruptedException ex)
24    {
25    }
```

Lines 4-8 The current date and time is inserted into the `Any`.

Lines 10-17 The event data, in this example date and time, are pushed to the event channel. From the push supplier's view the event channel is just a consumer implementing the `PushConsumer` interface.

Lines 19-25 After sleeping for one second, the steps above are repeated. The example's pull supplier works similarly to the push supplier, except that the event channel explicitly polls the supplier for new events. This is done by either `pull()` or `try_pull()`. The pull supplier doesn't see anything from the event channel but an object implementing the `PullConsumer` interface. The following example shows the basic layout of a pull supplier:

```

1 // Java
2 public Any pull()
3 {
4     java.util.Date date = new java.util.Date();
5     String s = "PullSupplier says: " + date.toString();
6
7     Any any = orb.create_any();
8     any.insert_string(s);
9
10    return any;
11 }
12
13 public Any
14 try_pull(BooleanHolder has_event)
15 {
16     has_event.value = true;
17
18     return pull();
19 }

```

Lines 4-8 Date and time are inserted into the `Any`.

Lines 13-19 In this example new event data can be provided at any time, so `try_pull()` always sets `has_event` to `true` in order to signal that an event is available. It then returns the actual event data.

After examining the most important aspects of the event suppliers' code, we are now going to analyze the consumers' code. The push consumer with its `push()` operation is shown first:

```
// Java
public void push(Any any)
{
    try
    {
        String s = any.extract_string();
        System.out.println(s);
    }
    catch(MARSHAL ex)
    {
        // Ignore unknown event data
    }
}
```

The push consumer's `push()` operation is called with the event wrapped in a CORBA `Any`. In this code fragment it is assumed that the `Any` contains a string with date and time information. In case the `Any` contains another data type a `MARSHAL` exception is thrown. This exception can be ignored here because other events aren't of interest. After extracting the string it is displayed in the console window.

In contrast to the push consumer, the pull consumer has to actively query the event channel for new events. This is how the pull consumer loop looks:

```

1 // Java
2 while(supplier_ != null)
3 {
4     Any any = null;
5
6     try
7     {
8         any = supplier_.pull();
9     }
10    catch(Disconnected ex)
11    {
12        // Supplier was diconnected from event channel
13    }
14
15    try
16    {
17        String s = any.extract_string();
18        System.out.println(s);
19    }
20    catch(MARSHAL ex)
21    {
22        // Ignore unknown event data
23    }
24 }

```

Line 4 A CORBA `Any` is prepared for later use.

Lines 6-13 Using `pull()`, the consumer polls the event channel for new events. The event channel acts as a pull supplier in this case. The `pull()` operation blocks until a new event is available.

Lines 15-23 The consumer expects a string wrapped in a CORBA `Any`. The string value is extracted and displayed. If an exception is raised the `Any` contained some other data type which is simply ignored.

In all of these examples the event channel acts either as a consumer (if the clients are suppliers) or a supplier (if the clients are consumers) of events. Actually each client is not directly connected to the event channel but to a proxy that receives or sends events on behalf of the channel. For more information on the Event Service and for the complete definitions of the IDL interfaces, please refer to the official Event Service specification.

The Interface Repository

A CORBA Interface Repository (IFR) is essential for applications using the dynamic features of CORBA, such as the Dynamic Invocation Interface and DynAny. The IFR holds IDL type definitions and can be queried and traversed by applications.

The Orbacus Interface Repository is compliant with [4]. This chapter does not provide a complete description of the IFR. For more information, please refer to the specification.

In this chapter

This chapter contains the following sections:

Usage	page 280
Connecting to the Interface Repository	page 284
Configuration Issues	page 285
Interface Repository Utilities	page 286
Programming Example	page 287

Usage

The Orbacus Interface Repository is currently only provided with Orbacus for C++, using this syntax:

```
irserv
  [-h,--help] [-v,--version] [-d,--debug] [-i,--ior]
  [-DNAME] [-DNAME=DEF] [-UNAME] [-IDIR]
  [--case-sensitive] [FILE ...]
```

-h --help	Display the command-line options supported by the server.
-v --version	Display the version of the server.
-d --debug	Print diagnostic messages. This option is for Orbacus internal debugging purposes only.
-i --ior	Print the stringified IOR of the server to standard output.
-DNAME -DNAME=DEF	Defines <code>NAME</code> as <code>DEF</code> , or <code>1</code> if <code>DEF</code> is not provided. This option is passed directly to the preprocessor.
-UNAME	Removes any definition for <code>NAME</code> . This option is passed directly to the preprocessor.
-IDIR	Adds <code>DIR</code> to the include file search path. This option is passed directly to the preprocessor.
--case-sensitive	The semantics of OMG IDL forbid identifiers in the same scope to differ only in case. This option relaxes these semantics, but is only provided for backward compatibility with non-compliant IDL.
FILE ...	IDL files to be loaded into the repository.

Windows Native Service

Syntax

Use the Windows Native Service as follows:

```
ntirservice
  [-h,--help] [-i,--install] [-s,--start-install]
  [-u,--uninstall] [-d,--debug]
```

-h --help	Display the command-line options supported by the server.
-i --install	Install the service. The service must be started manually.
-s --start-install	Install the service and start it.
-u --uninstall	Uninstall the service.
-d --debug	Run the service in debug mode.

In order to use the IFR as a native Windows service, it is first necessary to add the `ocf.ifr.endpoint` configuration property to the `HKEY_LOCAL_MACHINE` NT registry key (see [“Using the Windows Registry”](#) on [page 91](#) for more details).

Next the service should be installed with:

```
ntirservice -i
```

This adds the `Orbacus Interface Repository Service` entry to the `Services` dialog in the Control Panel. To start the naming service, select the `Orbacus Interface Repository Service` entry, and press `Start`. If the service is to be started automatically when the machine is booted, select the `Orbacus Interface Repository Service` entry, then click `Startup`. Next select `Startup Type - Automatic`, and press `OK`. Alternatively, the service could have been installed using the `-s` option, which configures the service for automatic start-up:

```
ntirservice -s
```

If you want to remove the service, run:

```
ntirservice -u
```

Note: If the executable for the Interface Repository is moved, it must be uninstalled and re-installed.

Any trace information provided by the service is placed in the Windows Event Viewer with the title `IRService`. To enable tracing information, add the desired trace configuration property (that is, one of the `ooc.orb.trace` properties) to the `HKEY_LOCAL_MACHINE` NT registry key with a `REG_SZ` value of at least 1.

Configuration Properties

In addition to the standard configuration properties described in [Chapter 4](#), the Orbacus Interface Repository also supports the following properties:

<code>ooc.ifr.options=OPTS</code>	Allows command-line options to be passed to the Windows Native service at start-up. Note that absolute pathnames should be used when specifying include directives, IDL files, etc.
<code>ooc.ifr.endpoint=ENDPOINT</code>	Specifies the endpoint configuration for the service. Note that this property is only used if the <code>ooc.orb.oa.endpoint</code> property is not set.

Connecting to the Interface Repository

The object key of the IFR is `DefaultRepository`, which identifies an object of type `CORBA::Repository`.

The object key can be used when composing URL-style object references. For example, the following URL identifies the IFR running on host `ifrhost` at port `10000`:

```
corbaloc::ifrhost:10000/DefaultRepository
```

Refer to [Chapter 6](#) for more information on URLs and configuring initial services.

Configuration Issues

Although applications can interact with the IFR as with any other CORBA server, it does have special status within the ORB. Specifically, use of the standard operation `Object::get_interface()` requires the presence of an IFR:

```
// PIDL
interface Object
{
    ...
    InterfaceDef get_interface();
    ...
};
```

The exact semantics of `get_interface` can be a source of confusion. In Orbacus, as with most other ORBs, the `get_interface` operation is a *remote* operation. That is, when a client invokes `get_interface` on an object reference, the request is sent to the server. The server knows the interface type of the object reference and interacts with the IFR to locate the appropriate `CORBA::InterfaceDef` object to return to the client. *Therefore, the server must be configured for the IFR. It is not necessary to configure the client for the IFR if the client's only interaction with the IFR is via `get_interface`.*

Interface Repository Utilities

irfeed

IDL files can be loaded into the IFR at runtime using `irfeed`. See the description of the `irserv` command for more information on the command-line options.

```
irfeed
  [-h,--help] [-v,--version] [-d,--debug]
  [-DNAME] [-DNAME=DEF] [-UNAME] [-IDIR] FILE ...
```

irdel

Type definitions can be removed from the IFR using `irdel`. See the description of the `irserv` command for more information on the command-line options.

```
irdel
  [-h,--help] [-v,--version] name ...
```

The `name` argument represents the scoped name of the type to be removed. A scoped name has the form `X::Y::Z`. For example, an interface `I` defined in a module `M` can be identified by the scoped name `M::I`.

Programming Example

Below is a simple example in Java that demonstrates how to obtain an `InterfaceDef` object and display its contents:

```
1 // Java
2 import org.omg.CORBA.*;
3 ...
4
5 org.omg.CORBA.ORB = ... // initialize the ORB
6 org.omg.CORBA.Object obj = ... // get object reference somehow
7
8 org.omg.CORBA.Object defObj = obj._get_interface_def();
9 if(defObj == null)
10 {
11     System.err.println("No Interface Repository available");
12     System.exit(1);
13 }
14
15 InterfaceDef def = InterfaceDefHelper.narrow(defObj);
16 org.omg.CORBA.InterfaceDefPackage.FullInterfaceDescription
17     desc = def.describe_interface();
18
19 int i;
20 System.out.println("name = " + desc.name);
21 System.out.println("id = " + desc.id);
22 System.out.println("defined_in = " + desc.defined_in);
23 System.out.println("version = " + desc.version);
24 System.out.println("operations:");
25 for(i = 0 ; i < desc.operations.length ; i++)
26 {
27     System.out.println(i + ": " + desc.operations[i].name);
28 }
29 System.out.println("attributes:");
30 for(i = 0 ; i < desc.attributes.length ; i++)
31 {
32     System.out.println(i + ": " + desc.attributes[i].name);
33 }
34 System.out.println("base_interfaces:");
35 for(i = 0 ; i < desc.base_interfaces.length ; i++)
36 {
37     System.out.println(i + ": " + desc.base_interfaces[i]);
38 }
```

Lines 5-8 After initializing the ORB and obtaining an object reference, we invoke `_get_interface_def`¹ on the object.

Lines 9-13 If no interface definition could be found, `_get_interface_def` returns nil.

Line 15 Narrow the object reference to `InterfaceDef`. We now have a reference to an object in the IFR that describes the most-derived type of our object reference.

Line 16 Request a complete description of the interface.

Lines 19-37 Print information about the interface, including the names of its operations and attributes.

A complete example of how to use the IFR can be found in the `ob/demo/repository` subdirectory.

1. Recent versions of the IDL-to-Java mapping introduced the `_get_interface_def` operation, which returns `org.omg.CORBA.Object` instead of `org.omg.CORBA.InterfaceDef`. Portable Java applications should use `_get_interface_def`. In C++, the operation is `_get_interface`.

Orbacus Balancer

<SmallCaps>Orbacus Balancer provides load balancing of client connections across a group of replicated objects. The load balancing service provided by <SmallCaps>Orbacus Balancer is transparent and interoperable with any CORBA client. However, the interface between the servers and the service is strictly proprietary.

In this chapter

This chapter contains the following sections:

Basic Concepts	page 290
Load Balancing Strategies	page 291
Service Security	page 294
Usage	page 295
Connecting to the Service	page 303
Load Balanced IMR-enabled Servers	page 304
Utilities	page 305
Programming Example	page 310

Basic Concepts

Let us assume that we wish to provide a library service that is made available through a set of objects. These objects being a set of book objects and a library object that manages the book objects. Furthermore, it is desired that connections made with each of these objects be load balanced. The replicated objects for each book and the replicated library objects are managed in the service by a single entity that is called a *load balanced group*. Each member of the load balanced group must provide a replica of each object — for the library service, each member must provide a replica of each book object and a replica of the library object.

All of the replicas provided by a member must be activated on a single POA with a *member* policy (which uniquely identifies the member within the service), the `USER_ID` ID assignment policy value, and the `PERSISTENT` lifespan policy value. Such a POA will be referred to as a *member POA* and the corresponding server will be referred to a *load balanced server*. Object references created by a member POA will refer to the service instead of the member POA within the load balanced server.

When a client makes a request on an object using a reference create by a member POA, the service:

- receives the request,
- determines the load balanced group,
- selects a member of this group, and
- returns a new reference to the client that refers to the replica of the object that is provided by this member.

The client then establishes a connection with the server using the new object reference and communicates directly with the server, without the intervention of the service.

Load Balancing Strategies

Each load balanced group within the service has an associated load balancing strategy. The load balancing strategy determines which member will be used to service the next client connection. The strategy is also responsible for load re-balancing. Load re-balancing is done by issuing load alerts to overload members. When a member receives a load alert, it forwards the next client request back to the service.

There are two types of strategies: adaptive and non-adaptive. When using an adaptive strategy, a load balanced group must receive load updates from the members. These loads are then used by the strategy to determine the next member to be used for a client connection. Adaptive strategies can also provide load re-balancing. When using non-adaptive strategies, the service does not require load updates from the members and load re-balancing is not possible.

Member selection and load re-balancing are discussed in the following sections. The advantages and disadvantages of the different types of load balancing strategies is also presented.

Member Selection

Non-adaptive member selection does not use load information from the members. Hence, non-adaptive member selection will only correctly balance connections under a certain set of conditions. These conditions are as follows:

- Dedicated hosts
- Homogeneous hosts
- Clients generate the same load and are connected for the same amount of time – or –clients are connected for short periods of time

While adaptive member selection can be used in more situations than non-adaptive member selection, it is not without problems. The problems with adaptive member selection are highlighted below:

1. Using a polling technique to retrieve member loads does not scale. Hence, it is decided that loads will be reported to the load balanced group at regular intervals by each member. However, this implies that

when making a load balancing decision, loads do not necessarily represent the current loads of the members, but instead past loads. This is a source of error.

These errors will be large when many clients connect in a short period of time. This is because the actual load of members will increase dramatically before the loads can be updated.

Increasing the frequency of load updates will decrease the error, but then the overhead of load balancing is increased due the extra network traffic. Hence, an optimum value must be discovered for each installation.

2. Another source of error is that spikes in the load of a member may cause bad load balancing decisions.
3. Yet another problem with load balancing is that, in most cases, it is difficult to estimate the load that a new client connection will impose on a member. This becomes a bigger problem on a heavily loaded system since a load balancing decision may cause a members load to increase well past the critical level.

Errors of this type can be alleviated by using load re-balancing. However, load re-balancing will introduce other sources of errors, as discussed in the next section.

Load Re-balancing

Load re-balancing is the transfer of a client connection from the replica of one member to the replica of another. This is achieved by getting a member to forward the next client request back to the service. Load re-balancing is useful when the loads of the members become imbalanced. Through load re-balancing these imbalances can be corrected, resulting in a higher average throughput. Several factors may contribute to a load imbalance:

- Clients not generating a consistent load while connected
- Clients not connected for the same amount of time
- Heterogeneous hosts
- Non-dedicated hosts
- Member selection errors

For effective load re-balancing, we must be able track client connections and the load generated by each connection. However, the concept of a connection is hidden from the CORBA developer, so in general, all that is

available is the load for each member of the load balanced group. Hence, we must make certain approximations when making load re-balancing decisions. For these approximations to hold, the following assumptions must be made:

- The average load created by a client can be reliably estimated
- The load created by a client does not deviate much from the average load
- Dedicated hosts
- Homogeneous hosts

Since load re-balancing decisions are based on approximations that will only be reasonable when certain conditions are meant, there is always the chance of a load re-balancing error. Let us say that a load re-balancing error occurs when the load that is transferred from the replica of one member to the replica of another causes the target member to become overloaded. This situation is what we will call system instability. In some cases the system may remain unstable indefinitely. For example, if a single client is solely responsible for causing a high load, then the client will likely be bounced from member to member. Yet another source of load re-balancing errors comes from the fact that a member cannot redirect a client until it receives a request. When this occurs, the member may no longer be overloaded. This can be alleviated by associating an expire time with a load alert.

Choosing a Load Balancing Strategy

Some important things to note when choosing between adaptive and non-adaptive load balancing strategies are:

- Non-adaptive strategies impose very little overhead compared to adaptive strategies.
- Adaptive strategies will produce a more balanced system when the assumptions for the non-adaptive strategies are not satisfied.

Under certain conditions, load re-balancing will be error-prone. In such a case, adaptive strategies which take an aggressive approach to re-balancing may result in many load re-balancing errors. Furthermore, load re-balancing can be an expensive operation, making these errors even more severe. On the other hand, if the system is such that load re-balancing errors seldom occur and the expense of re-balancing is minimal, then adaptive strategies that take an aggressive approach to load re-balancing should result in a higher average throughput due to a more balanced system.

Service Security

It is very important that only <SmallCaps>Orbacus Balancer's public port (also referred to as its forward port) be accessible outside of the network firewall. Otherwise, anyone can mimic the members of a load balanced group causing a *denial of service*.

For additional security, many of the operations on the service are only allowed when the service is running in *administrative* mode. That is:

- creating and destroying load balanced groups,
- setting the load balancing strategy, and
- adding or removing members

are only possible when the service is running in administrative mode. An attempt to perform these operations when it is not running in administration mode will result in a `CORBA::NO_PERMISSION` exception.

Usage

<SmallCaps>Orbacus Balancer is currently only implemented using Orbacus for C++, but Orbacus for Java servers can also be load balanced. <SmallCaps>Orbacus Balancer command line usage is as follows:

```
balancer
  [-h,--help] [-v,--version] [-a,--administrative]
  [-d,--database] [-A,--admin-endpoint]
  [-F,--forward-endpoint]
```

-h, --help	Display the command-line options supported by the server.
-v, --version	Display the version of the server.
-a, --administrative	Run the service in administrative mode. The service will run in non-administrative mode by default.
-d DIRECTORY, --database DIRECTORY	Specifies the directory in which the service maintains its database files. If not specified, then the current working directory is used.
-A INFO, --admin-endpoint INFO	Specifies the service's administrative public endpoint settings. This is the endpoint that the load balanced servers use to communicate with the service. For security reasons, access to this endpoint can be restricted.
-F INFO, --forward-endpoint INFO	Specifies the services's public endpoint settings, which is used by clients for server requests.

Windows Native Service

The balancer server is also available as a native Windows service.

```
ntbalancerservice
  [-h,--help] [-i,--install] [-s,--start-install]
  [-u,--uninstall] [-d,--debug]
```

-h --help	Display the command-line options supported by the service.
-i --install	Install the service. The service must be started manually.
-s --start-install	Install and start the service.
-u --uninstall	Uninstall the service.
-d --debug	Run the service in debug mode.

In order to use <SmallCaps>Orbacus Balancer as a native Windows service, first add the desired configuration properties to the `HKEY_LOCAL_MACHINE` NT registry key (see [“Using the Windows Registry”](#) on page 91 for more details). For example, add the `ooc.balancer.admin_endpoint` and `ooc.balancer.forward_endpoint` properties so that the service will use non-default ports.

Next the service should be installed with:

```
ntbalancerservice -i
```

This adds the Orbacus Balancer entry to the Services dialog in the Control Panel. To start the service, select the Orbacus Balancer entry, and press *Start*. If the service is to be started automatically when the machine is booted, select the Orbacus Balancer entry, then click *Startup*. Next select *Automatic* for the Startup Type and press *OK*. Alternatively, the service could have been installed using the `-s` option, which configures the service for automatic start-up:

```
ntbalancerservice -s
```

If you want to remove the service, run:


```
ntbalancerservice -u
```

Note: If the executable for the service is moved, it must be uninstalled and re-installed.

Any trace information provided by the service is placed in the Windows Event Viewer with the title `Balancer`. To enable tracing information, add the desired trace configuration property (that is, one of the `ooc.balancer.trace` properties or one of the `ooc.orb.trace` properties) to the `HKEY_LOCAL_MACHINE` NT registry key with a `REG_SZ` value of at least 1.

Configuration Properties

In addition to the standard configuration properties described in Chapter , <SmallCaps>Orbacus Balancer also supports the following properties:

ooc.balancer.administrative

Value: `true`, `false`

If set to `true`, then run the service in administrative mode. For details refer to the `-a` command-line option.

ooc.balancer.dbdir

Value: *directory*

Equivalent to the `-d` command-line option.

ooc.balancer.admin_endpoint

Value: *info*

Equivalent to the `-A` command-line option.

ooc.balancer.forward_endpoint

Value: *info*

Equivalent to the `-F` command-line option.

ooc.balancer.trace.database

Value: *level* ≥ 0

Defines the output level for database diagnostic messages printed by the service. The default level is 0, which produces no output. A level of 1 or higher produces database information (for example, loading, adding and removing group records in the database).

ooc.balancer.trace.lifecycle

Value: *level* ≥ 0

Defines the output level for lifecycle diagnostic messages printed by the service. The default level is 0, which produces no output. A level of 1 or higher produces lifecycle information (for example, creation and destruction of load balanced groups, adding and removing members, and setting load balancing strategies).

ooc.balancer.trace.load_balance

Value: *level* ≥ 0

Defines the output level for diagnostic messages related to the load balancing of members. The default level is 0, which produces no output. Levels greater than 0 produce different degrees of output.

Built-in Load Balancing Strategies

In this section we present the load balancing strategies that are provided with <SmallCaps>Orbacus Balancer. Note that the default strategy is the *round-robin* strategy.

random

Non-adaptive strategy where members are selected at random. There are no configuration properties for this strategy.

round-robin

Non-adaptive strategy where members are selected in round-robin order. There are no configuration properties for this strategy.

least-load

Adaptive strategy where the least loaded members are chosen in round-robin order. The configuration properties for this strategy are as follows:

tolerance

Type: CORBA::ULong

Members with a load difference that is less than `tolerance` are considered to have the same load. The default value for this property is 0.

This alleviates the member selection problem 1. on page 291.

load-per-client

Type: CORBA::ULong

The `load-per-client` property is an estimate of the load for a given client connection. It is used so that a member's load can be adjusted without having to wait for the next load update. It is also used to estimate the effect of load re-balancing. The default value for this property is 0.

This alleviates the member selection problem 1. on page 291.

critical-load

Type: CORBA::ULong

A member with a load greater than `critical-load` is re-balanced if there exists a member with a load that is less than `critical-load` minus `load-per-client`. This property has a default value of 0, which disables load re-balancing.

This alleviates the member selection problem 3. on page 292.

reject-load

Type: CORBA::ULong

A connection request will be rejected if all members have a load greater than the `reject-load` property. This property has a default value of 0, which means that connections will never be rejected.

dampening-multiplier

Type: CORBA::Float

A dampening technique is used to smooth out spikes that may occur in the reported loads of members. The load of a member is calculated using the `dampening-multiplier` property as follows:

$$\text{load} = \text{mult} * \text{old_load} + (1 - \text{mult}) * \text{new_load}$$

where `mult` is the value of the `dampening-multiplier` property. This property must be greater than or equal to 0 and less than 1. The default value of 0, which disables dampening.

This alleviates member selection problems 1. on page 291 and 2. on page 292.

min-dispersion

Adaptive strategy which attempts to keep the member loads within a given tolerance. This strategy takes an aggressive approach to load re-balancing. The configuration properties for this strategy are as follows:

tolerance

Type: CORBA::ULong

Members with loads less than the average minus the `tolerance` are selected in round-robin order. Members with loads greater than the average plus the `tolerance` are re-balanced. If there are no members with loads less than the average minus the `tolerance`, then members with loads within `tolerance` of the average are selected in round-robin order. The default value for this property is 0.

This alleviates the member selection problem 1. on page 291 and 3. on page 292.

load-per-clientSee [“load-per-client” on page 300.](#)**reject-load**See [“reject-load” on page 301.](#)

dampening-multiplier

See [“dampening-multiplier”](#) on page 301.

Connecting to the Service

Servers that use <SmallCaps>Orbacus Balancer must be configured with the service's initial reference. The object key of the service is `Balancer`, hence, a URL-style object reference of the service running on host `lbhost` at port `10000` would be:

```
corbaloc::lbhost:10000/Balancer
```

Using this object reference, a server can configure the <SmallCaps>Orbacus Balancer initial reference with the property:

```
ooc.orb.service.Balancer=corbaloc::lbhost:10000/Balancer
```

An alternative to using the above property is to use the `-ORBInitRef` command-line option. Refer to [Chapter 6](#) for more information on URLs and configuring initial services.

Load Balanced IMR-enabled Servers

Load balanced servers may also be IMR-enabled servers. For information on using the IMR, refer to [Chapter 7](#). Note that <SmallCaps>Orbacus Balancer and the IMR need no additional configuration.

Object references created by a member POA of an IMR-enabled server will still refer to the associated load balanced group within <SmallCaps>Orbacus Balancer. However, when <SmallCaps>Orbacus Balancer selects a member implemented by a IMR-enabled server to service a new connection, the reference returned to the client will actually refer to the IMR instead of the member's server. When the client makes a request using this reference, the IMR receives the request, activates the member's server (if necessary) using the OAD, and returns a new object reference to the client that refers the server.

Utilities

In this section

This section describes various load balancing utilities:

Service Administration	page 306
Making References	page 307
Utility Objects	page 308
Utility Object Configuration Properties	page 309

Service Administration

The `lbadmin` utility provides complete control over <SmallCaps>Orbacus Balancer. Its command interface is shown below:

<code>-h, --help</code>	Display this information.
<code>--list-groups</code>	List the load balanced groups.
<code>--create-group <i>group-id</i></code>	Create a load balanced group.
<code>--destroy-group <i>group-id</i></code>	Destroy a load balanced group.
<code>--get-group-info <i>group-id</i></code>	Get the attributes of a group.
<code>--get-group-ior <i>group-id repository-id object-id</i></code>	Get the IOR for use by a client.
<code>--set-strategy <i>group-id</i> <strategy></code>	Use the specified built-in strategy.
<code>--set-custom-strategy <i>group-id ior</i></code>	Use the given custom strategy.
<code>--list-members <i>group-id</i></code>	Enumerate the members of the group.
<code>--add-member <i>group-id member-id</i></code>	Add a member to the group.
<code>--remove-member <i>group-id member-id</i></code>	Remove a member from the group.
<code>--shutdown</code>	Shutdown the service.

Where <strategy> can be `random`, `round-robin`, `least-load`, or `min-dispersion`. The `least-load` strategy has the options:

```
--tolerance tolerance
--load-per-client load_per_client
--critical-load critical_load
--reject-load reject_load
--dampening-multiplier dampening_multiplier
```

The `min-dispersion` strategy has the options:

```
--tolerance tolerance
--load-per-client load_per_client
--reject-load reject_load
--dampening-multiplier dampening_multiplier
```

Making References

The `lbmkref` utility creates object references for use by clients of <SmallCaps>Orbacus Balancer. Note that this can only be used to create object references when the service is configured to use the IOP. Its usage is shown below.

```
lbmkref [-H host] port group-id repository-id object-id
```

<i>host</i>	The host that the <code>balancer</code> server is running on. The default value is the canonical hostname of the machine in which <code>lbmkref</code> is executed.
<i>port</i>	The forward port of the service.
<i>group-id</i>	The ID of the load balanced group.
<i>repository-id</i>	The Repository ID of the new object reference.
<i>object-id</i>	The Object ID of the new object reference.

Utility Objects

To take advantage of the features of the adaptive load balancing strategies, a load balanced server must send load updates to the appropriate load balanced groups and respond to load alerts. <SmallCaps>Orbacus Balancer provides utility objects that the developer may use to help implement this functionality.

The utility objects provided by <SmallCaps>Orbacus Balancer are part of the `LoadBalancing::Util` module and are provided as initial services (see “[The BootManager](#)” on page 166). Each utility object is described below. For further detail, refer to [Appendix F](#), and for an example refer to “[Adaptive Load Balancing](#)” on page 315.

LoadAlert

The LoadAlert object is used to manage load alerts sent by the service. The name of the LoadAlert initial service is `LoadAlert`.

LoadCalculator

The LoadCalculator object is used by the LoadUpdater object (see below) to calculate the current load of the server (which will be used as the load of each member registered with the LoadUpdater object). The implementation provided by the service calculates the load based on the number of active requests.

LoadUpdater

The LoadUpdater object is used to manage load updates sent to the Balancer. At regular intervals the LoadUpdater object gets the load from the LoadCalculator object and pushes it to the load balanced group of each registered member.

Utility Object Configuration Properties

The <SmallCaps>Orbacus Balancer utility objects support the following properties:

ooc.balancer.util.create_alert

Value: `true, false`

If set to true, then the LoadAlert object will be created and will be available as an initial service. The default value is true.

ooc.balancer.util.create_calculator

Value: `true, false`

If set to true, then the LoadCalculator object will be created and will be available as an initial service. The default value is true.

ooc.balancer.util.create_updater

Value: `true, false`

If set to true, then the LoadUpdater object will be created and will be available as an initial service. The default value is true. If the LoadCalculator object is also created, then this object does not have to be set in the LoadUpdater object.

ooc.balancer.trace.alert_expire

Value: `timeout >= 0`

Specifies the expiry time for a load alert in milliseconds. The default is 1000 (1 second). A value of 0 means that load alerts never expire.

ooc.balancer.trace.load_update

Value: `frequency >= 0`

Specifies the load update frequency for the LoadUpdater object in milliseconds. The default is 1000 (1 second). A value of 0 means that no load updates will be sent to the service.

Programming Example

Implementing a Load Balanced Server

In this section, we will show how to modify the C++ version of the Hello World server (see [Chapter 2](#)) for load balancing. First we will present the modifications necessary for non-adaptive load balancing, then the necessary modifications for adaptive load balancing will be presented. This is followed by a description of the steps necessary to configure the service for the load balanced Hello World servers.

In this section

This section covers the following topics:

Non-adaptive Load Balancing	page 311
Adaptive Load Balancing	page 315
Running the Load Balanced Servers	page 320

Non-adaptive Load Balancing

The Hello World server presented in Chapter uses the Root POA to activate its Hello servant. However, a member POA must have a member policy, the `USER_ID` ID assignment policy value and the `PERSISTENT` lifespan policy value. Hence, the Hello World server must be modified so that the Hello servant is activated using a POA with the above policies. Furthermore, the Hello servant is no longer activated under the Root POA, so it becomes necessary for it to override the `_default_POA` method. The modified servant's class declaration is shown below:

```
1 // C++
2 #include <Hello_skel.h>
3
4 class Hello_impl : public POA_Hello,
5                   public PortableServer::RefCountServantBase
6 {
7     PortableServer::POA_var poa_;
8
9 public:
10
11     Hello_impl(PortableServer::POA_ptr);
12
13     virtual void say_hello() throw(CORBA::SystemException);
14
15     virtual PortableServer::POA_ptr _default_POA();
16 };
```

Line 7 Private member to store the servant's default POA.

Line 11 A constructor must be defined to allow the assignment of the servant's default POA.

Line 15 Declaration of the `_default_POA` method.

The remainder of the class declaration is unchanged. The definition of the constructor and `_default_POA` method follow:

```
// C++
Hello_impl::Hello_impl(PortableServer::POA_ptr poa)
    : poa_(PortableServer::POA::_duplicate(poa))
{
}

PortableServer::POA_ptr Hello_impl::_default_POA()
{
    return PortableServer::POA::_duplicate(poa_);
}
```

The modified server program is shown below :

```
1 // C++
2 #include <OB/CORBA.h>
3 #include <OB/Balancer_init.h>
4 #include <Hello_impl.h>
5
6 int run(CORBA::ORB_ptr, int, char*[]);
7
8 int main(int argc, char* argv[])
9 {
10     int status = EXIT_SUCCESS;
11     CORBA::ORB_var orb;
12
13     try
14     {
15         LoadBalancing::LB_init();
16         orb = CORBA::ORB_init(argc, argv);
17         status = run(orb, argc, argv);
18     }
19     catch(const CORBA::Exception&)
20     {
21         status = EXIT_FAILURE;
22     }
23
24     if(!CORBA::is_nil(orb))
25     {
26         try
27         {
28             orb -> destroy();
29         }
```



```

30     catch(const CORBA::Exception&)
31     {
32         status = EXIT_FAILURE;
33     }
34 }
35
36 return status;
37 }

```

Line 3 Include the header file that declares the <SmallCaps>Orbacus Balancer initialization function. This header file also includes the header files `OB/Balancer.h` and `OB/BalancerPolicyTypes.h`, which contain the definitions necessary for non-adaptive load balancing.

Line 15 Invoke `LoadBalancing::LB_init()`. This function initializes the server for load balancing and must be called before initializing the ORB. The remainder of the `main()` function is similar to the one shown in [Chapter 2 on page 25](#). Now we write the `run()` function:

```

1 // C++
2 int run(CORBA::ORB_ptr orb, int argc, char* argv[])
3 {
4     if(argc != 2)
5         return EXIT_FAILURE;
6     const char* memberId = argv[1];
7
8     CORBA::Object_var poaObj =
9         orb -> resolve_initial_references("RootPOA");
10    PortableServer::POA_var rootPoa =
11        PortableServer::POA::_narrow(poaObj);
12
13    PortableServer::POAManager_var manager =
14        rootPoa -> the_POAManager();
15
16    LoadBalancing::MemberPolicyValue_var value =
17        new LoadBalancing::MemberPolicyValue();
18    value -> group_id = CORBA::string_dup("Hello");
19    value -> member_id = CORBA::string_dup(memberId);
20    CORBA::Any any;
21    any <<= value._retn();
22    CORBA::Policy_var memberPolicy =
23        orb -> create_policy(LoadBalancing::MEMBER_POLICY_ID,
24        any);
24

```

```

25     CORBA::PolicyList pl(3);
26     pl.length(3);
27     pl[0] = rootPOA -> create_lifespan_policy(
28         PortableServer::PERSISTENT);
29     pl[1] = rootPOA -> create_id_assignment_policy(
30         PortableServer::USER_ID);
31     pl[3] = memberPolicy;
32     PortableServer::POA_var helloPOA =
33         rootPOA -> create_POA("hello", manager, pl);
34
35     Hello_impl* helloImpl = new Hello_impl(helloPOA);
36     PortableServer::ServantBase_var servant = helloImpl;
37     PortableServer::ObjectId_var oid =
38         PortableServer::string_to_ObjectId("hello");
39     helloPOA -> activate_object_with_id(oid, servant);
40     Hello_var hello = helloImpl -> _this();
41
42     manager -> activate();
43     orb -> run();
44
45     return EXIT_SUCCESS;
46 }

```

Lines 4-6 Check the arguments for the member ID.

Lines 16-23 Create the member policy. The group ID will be `Hello` and the member ID is an argument of the program.

Lines 25-33 Create the member POA.

Lines 35-40 Create the Hello servant and activate it on the member POA. The remainder of the `run()` function is similar to that of [Chapter 2 on page 25](#).

Adaptive Load Balancing

To use adaptive load balancing, the Hello server must send load updates to the service and react to load alerts. The <SmallCaps>Orbacus Balancer utility objects will be used to help implement this functionality. The modified server program is shown below:

```
1 // C++
2 #include <OB/CORBA.h>
3 #include <OB/Balancer_init.h>
4 #include <OB/BalancerUtil_init.h>
5 #include <OB/Balancer_skel.h>
6 #include <Hello_impl.h>
7
8 class LoadAlert_impl :
9     virtual public POA_LoadBalancing::LoadAlert,
10    virtual public PortableServer::RefCountServantBase
11 {
12     LoadBalancing::Util::LoadAlert_var alert_;
13
14 public:
15     LoadAlert_impl(LoadBalancing::Util::LoadAlert_ptr alert)
16         :
17         alert_(LoadBalancing::Util::LoadAlert::_duplicate(alert))
18     {
19
20     virtual void alert()
21         throw(CORBA::SystemException)
22     {
23         alert_ -> alert();
24     }
25 };
26
27 int run(CORBA::ORB_ptr, int, char*[]);
28
29 int main(int argc, char* argv[])
30 {
31     int status = EXIT_SUCCESS;
32     CORBA::ORB_var orb;
33
```

```

34 try
35     {
36         LoadBalancing::LB_init();
37         LoadBalancing::Util::LBUtil_init();
38         orb = CORBA::ORB_init(argc, argv);
39         status = run(orb, argc, argv);
40     }
41     catch(const CORBA::Exception&)
42     {
43         status = EXIT_FAILURE;
44     }
45
46     if(!CORBA::is_nil(orb))
47     {
48         try
49         {
50             orb -> destroy();
51         }
52         catch(const CORBA::Exception&)
53         {
54             status = EXIT_FAILURE;
55         }
56     }
57
58     return status;
59 }

```

Line 4 Include the header file that declares the <SmallCaps>Orbacus Balancer utility initialization function. This header file also includes the header file `OB/BalancerUtil.h`, which contain the definitions of the utility objects.

Line 5 The header file `OB/Balancer_skel.h` must be included for the implementation of the `LoadBalancing::LoadAlert` interface.

Lines 8-25 An implementation of the `LoadBalancing::LoadAlert` interface that delegates to the `LoadAlert` utility object.

Line 37 Invoke `LoadBalancing::Util::LBUtil_init()`. This function initializes the utility objects and must be called before initializing the ORB.

The remainder of the main() function is the same as in section [“Non-adaptive Load Balancing” on page 311](#). Now we write the run() function:

```

1 // C++
2 int run(CORBA::ORB_ptr orb, int argc, char* argv[])
3 {
4     if(argc != 2)
5         return EXIT_FAILURE;
6     const char* memberId = argv[1];
7
8     CORBA::Object_var poaObj =
9         orb -> resolve_initial_references("RootPOA");
10    PortableServer::POA_var rootPoa =
11        PortableServer::POA::_narrow(poaObj);
12
13    PortableServer::POAManager_var manager =
14        rootPoa -> the_POAManager();
15
16    LoadBalancing::MemberPolicyValue_var value =
17        new LoadBalancing::MemberPolicyValue();
18    value -> group_id = CORBA::string_dup("Hello");
19    value -> member_id = CORBA::string_dup(memberId);
20    CORBA::Any any;
21    any <<= value._retn();
22    CORBA::Policy_var memberPolicy =
23        orb -> create_policy(LoadBalancing::MEMBER_POLICY_ID,
24    any);
25
26    CORBA::PolicyList pl(3);
27    pl.length(3);
28    pl[0] = rootPOA -> create_lifespan_policy(
29        PortableServer::PERSISTENT);
30    pl[1] = rootPOA -> create_id_assignment_policy(
31        PortableServer::USER_ID);
32    pl[3] = memberPolicy;
33    PortableServer::POA_var helloPOA =
34        rootPOA -> create_POA("hello", manager, pl);
35
36    Hello_impl* helloImpl = new Hello_impl(helloPOA);
37    PortableServer::ServantBase_var servant = helloImpl;
38    PortableServer::ObjectId_var oid =
39        PortableServer::string_to_ObjectId("hello");
40    helloPOA -> activate_object_with_id(oid, servant);
41    Hello_var hello = helloImpl -> _this();
42

```

```

42     CORBA::Object_var obj =
43         orb -> resolve_initial_references("Balancer");
44     LoadBalancing::GroupFactory_var factory =
45         LoadBalancing::GroupFactory::_narrow(obj);
46
47     obj = orb -> resolve_initial_references("LoadUpdater");
48     LoadBalancing::Util::LoadUpdater_var updater =
49         LoadBalancing::Util::LoadUpdater::_narrow(obj);
50
51     obj = orb -> resolve_initial_references("LoadAlert");
52     LoadBalancing::Util::LoadAlert_var alert =
53         LoadBalancing::Util::LoadAlert::_narrow(obj);
54
55     LoadAlert_impl* loadAlertImpl = new LoadAlert_impl(alert);
56     PortableServer::ServantBase_var alertServant =
57         loadAlertImpl;
58     LoadBalancing::LoadAlert_var loadAlert =
59         loadAlertImpl -> _this();
60
61     manager -> activate();
62
63     LoadBalancing::Group_var group = factory -> get("Hello");
64     group -> set_load_alert(memberId, loadAlert);
65
66     updater -> register_member(memberId, "Hello");
67
68     orb -> run();
69
70     return EXIT_SUCCESS;
71 }

```

Lines 25-33 Create the member POA.

Lines 42-53 Get the GroupFactory and the LoadUpdater and LoadAlert utility objects.

Lines 55-58 Create the LoadAlert servant and activate it on the root POA.

Lines 62-63 Set the member's LoadAlert object. Note that this should be done after activating the POA manager since it may result in a request to this server.

Line 65 Register the member with the LoadUpdater.

The remainder of the `run()` function is the same as in section [“Non-adaptive Load Balancing”](#) on page 311.

Running the Load Balanced Servers

In this section we present the step required to set up the <SmallCaps>Orbacus Balancer for the Hello World load balanced servers. We will assume that Orbacus has been installed in the directory `/usr/local/Orbacus` and the executables `balancer`, `lbadm` and `lbmkref` all exist in a directory that is in the search path. The steps are as follows:

1. Create a configuration file for <SmallCaps>Orbacus Balancer containing the following:

```
# balancer.conf
ooc.balancer.admin_endpoint=iiop --port 10000
ooc.balancer.forward_endpoint=iiop --port 10001
ooc.balancer.dbdir=/usr/local/Orbacus/db
```

This file is placed in the `/usr/local/Orbacus/etc` directory.

2. Start the service in administrative mode:

```
balancer -ORBconfig /usr/local/Orbacus/etc/balancer.conf \
--administrative
```

3. Create the load balanced group.

Before starting the load balanced servers, the associated load balanced group must be created. This can be done using the `lbadm` utility as follows:

```
lbadm -ORBInitRef Balancer=corbaloc::lbhost:10000/Balancer\
--create-group Hello
```

Where `lbhost` is the host running the service.

4. Add the members.

The members can be added to the group explicitly using the `--add-member` command of the `lbadm` utility or they can be added automatically when the load balanced servers are started.

Note that members cannot be added automatically by the load balanced servers if the service is not running in administrative mode.

5. Configure the load balancing strategy.

The `--set-strategy` or `--set-custom-strategy` commands of the `lbadm` utility may be used to configure the group's load balancing strategy. For example, to use the `least-load` strategy:


```
lbadmin -ORBInitRef Balancer=corbaloc::lbhost:10000/Balancer\
  --set-strategy least-load \
  --tolerance 5 --load-per-client 5
```

Note that the strategy may also be changed after the load balanced servers are started.

6. Start the load balanced servers. For example, to start a server for the member with ID `member1`, run:

```
server -ORBInitRef Balancer=corbaloc::lbhost:10000/Balancer \
  member1
```

7. Create object references for use by the clients.

To create an object reference run:

```
lbmkref -H lbhost 10001 Hello IDL:Hello:1.0 Hello > Hello.ref
```

Note that the object references created by the load balanced servers can also be used by the clients.

After all members have been registered and the load balancing strategy is configured, it is recommended to restart the service in non-administrative mode. This will prevent any accidental (or unauthorized) modifications.

Orbacus Watson

Orbacus Watson is a loadable module that provides request tracing capabilities based on Portable Interceptors. Method names, parameter and return values, exceptions and a call stack can be visualized. The module can be loaded dynamically at application startup (when shared libraries are used) or linked statically to an application.

In this chapter

This chapter contains the following sections:

Tracing Levels	page 324
Installing Watson in C++	page 325
Installing Watson in Java	page 326
Configuration Properties	page 327

Tracing Levels

The level of request tracing is controlled by the properties described in the next section. The default value for all tracing levels is 0.

0	no tracing
1	displays name, request id, return/exception status of operation
2	displays parameters and return values
3	displays the call stack
4	displays object id, adapter id, effective profile

The tracing levels are cumulative; that is, the higher levels include the output generated by the lower levels. In order to make request parameters, results and exceptions available for tracing the option `--with-interceptor-args` has to be specified to the IDL compiler.

Installing Watson in C++

If Orbacus was built with shared libraries or DLLs, Orbacus Watson can be installed dynamically by defining the following configuration properties:

```
ooc.orb.modules=watson
ooc.orb.module.watson=<library-name>
```

Please refer to [Chapter 4](#) for more information on these properties.

If Orbacus was built statically, the module initialization function has to be called directly from the application code:

```
1 // C++
2 #if !defined(HAVE_SHARED) && !defined(OB_DLL)
3 #include <OB/watson.h>
4 #endif
5
6 int main(int argc, char* argv[])
7 {
8     CORBA::ORB_var orb;
9     ...
10 #if !defined(HAVE_SHARED) && !defined(OB_DLL)
11     //
12     // When linking statically, we need to explicitly
13     initialize
14     // Watson
15     //
16     init_module_watson();
17 #endif
18     orb = CORBA::ORB_init(argc, argv);
19     ...
20 }
```

Lines 2-4 Include `OB/watson.h` only when building statically.

Lines 10-16 Explicitly install the Watson module prior to initializing the ORB.

Specifying the configuration property `ooc.orb.modules=watson` will result in an (informative) error message from the ORBs ModuleManager upon application startup if the module was linked statically.

Installing Watson in Java

Since Orbacus Watson is based on Portable Interceptors, it is installed using the standard mechanism for installing interceptors. Specifically, a property is defined which specifies the name of a class to be loaded:

```
org.omg.PortableInterceptor.ORBInitializerClass.com.ooc.watson.RI  
ORBInitializer_impl
```

Note that the property has no associated value, as the name of the class to be loaded is part of the property name.

Configuration Properties

The behavior of the Orbacus Watson module is controlled by the following properties.

Property	Description
<code>ooc.watson.trace.requests=<level></code>	This property sets the indicated tracing level for the <code>in</code> and <code>out</code> direction. The default value is 0.
<code>ooc.watson.trace.requests.in=<level></code>	This property sets the indicated tracing level only for the <code>in</code> direction. The default value is 0.
<code>ooc.watson.trace.requests.out=<level></code>	This property sets the indicated tracing level only for the <code>out</code> direction. The default value is 0.

The information displayed in the `in` and `out` directions differ for the different roles an application takes in CORBA. For a client application making a CORBA request, the `out` direction corresponds to the request sending direction and the results are received in the `in` direction. For a server application, requests from clients are coming `in` and replies with results or exceptions are sent `out`.

Setting one of the more specific properties (`ooc.watson.trace.requests.in` and `ooc.watson.trace.requests.out`) overrides the corresponding value for this direction set by `ooc.watson.trace.requests`.

Sample Configuration File

Applications using Orbacus Watson can simply be started by specifying a configuration file with appropriate property settings with the `-ORBconfig` command-line option:

```
server -ORBconfig watson.cfg
```

The following example file shows how to set properties for C++ and Java applications:

```
#
# Register ORB initializer for watson (Orbacus/Java)
#
org.omg.PortableInterceptor.ORBInitializerClass.com.ooc.watson.R
IORBInitializer_impl

#
# Load module watson (Orbacus/C++)
#
# Disable if module was build statically to avoid
# error message from the ORBs ModuleManager
#
ooc.orb.modules=watson

#
# On Windows, enable one of the following properties
# if you built with DLLs
#
# For debug builds:
#
#ooc.orb.module.watson=watson412d.dll
#
# For non-debug builds:
#
#ooc.orb.module.watson=watson412.dll

#
# Set request tracing levels
# - more specific settings (.in and .out) override the
# general setting in the first of these lines
#
ooc.watson.trace.requests=3
ooc.watson.trace.requests.in=1
ooc.watson.trace.requests.out=2
```


Using Policies

This chapter describes the policies used to configure the ORB and to create a new POA. These policies are derived from the interface CORBA::Policy.

In this chapter

This chapter contains the following sections:

Overview	page 330
Supported Policies	page 331
Programming Examples	page 334

Overview

The ORB and its services may allow the application developer to configure the semantics of its operations. This configuration is accomplished in a structured manner through interfaces derived from the interface

`CORBA::Policy`.

There are two basic types of policies: those used to configure the ORB and those used to create a new POA. Furthermore, the configuration of ORB policy objects is accomplished at two levels:

- **ORB Level:** These policies override the system defaults. The ORB has an initial reference `ORBPolicyManager`. A `PolicyManager` has a set of operations through which the current set of overriding policies can be obtained, and new policies can be applied.
- **Object Level:** The object interface contains operations to retrieve and set policies for itself. Policies applied at the object level override those applied at the thread level, or the ORB level.

For more information on Policies, the `PolicyManager` interface and the `CORBA::Object` policy operations see [\[8\]](#) and [\[4\]](#).

Supported Policies

The following is a brief description of the Orbacus-specific policies that are currently supported. For a detailed description, please refer to [Appendix B](#). For standard policies, please refer to [\[4\]](#).

Table 4: *Orbacus policies*

Policy	Description
BiDirPolicy::BidirectionalPolicy	<p>This policy is used to enable CORBA 3 compliant BiDir GIOP functionality on both the Object and POA levels. Enabling this policy with a value of BiDirPolicy::BOTH on both levels will result in connection reuse when the server is required to make requests to the client.</p> <p>The default value is BiDirPolicy::NORMAL (disabled BiDir functionality). Both the client object and server POA needs this policy set to BOTH for BiDir communication to take place.</p>
OB::ACMTimeoutPolicy	<p>This policy determines whether the ORB performs active connection management (ACM) on the connection associated with an object reference. The policy specifies a time after which idle connections are shutdown. A value of 0 means no timeout. The default for this policy is the value of the <code>ooc.orb.client_timeout</code> property (see “ooc.orb.client_timeout” on page 79).</p>
OB::ConnectionReusePolicy	<p>This policy determines whether the ORB is permitted to reuse a communications channel between peers. If this policy is <code>false</code> then each object will have a new communications channel to its peer. The default for this policy is <code>true</code>.</p>
OB::ConnectTimeoutPolicy	<p>If an object has this policy and a connection cannot be established after <code>value</code> milliseconds, a <code>CORBA::NO_RESPONSE</code> exception is raised.</p>

Table 4: *Orbacus policies*

Policy	Description
OB::InterceptorPolicy	This policy determines whether client-side interceptors will be called. Client-side interceptors are enabled by default. To disable client-side interceptors, this policy can be set on an ORB or object reference with a value of <code>false</code> .
OB::LocateRequestPolicy	This policy determines whether the ORB sends GIOP LocateRequest messages. This policy exists to avoid an interoperability issue regarding the formatting of GIOP 1.2 LocateReply messages. Orbacus uses the correct formatting as of version 4.1. Unfortunately, all versions of Orbacus 4.0.x use the incorrect formatting, as do some other ORB implementations. As a result, the default value of this policy is <code>false</code> , which means the ORB will not send LocateRequest messages, and therefore will not receive improperly formatted replies.
OB::LocationTransparencyPolicy	This policy determines how strictly the ORB will enforce location transparency. The default behavior is relaxed. An application may wish to sacrifice performance to have strict CORBA compliance for local invocations.
OB::ProtocolPolicy	This policy allows an application to influence how the ORB orders and filters the profiles of an object reference. The value of the policy is a list of transport plug-in identifiers which determine the preferred order in which the ORB should attempt to establish connections. Only those profiles which match an entry in the list will be used. If no profile from the object reference matches a transport in the list, or the ORB was unable to establish a connection, then a <code>TRANSIENT</code> exception is raised.
OB::RequestTimeoutPolicy	If an object has this policy and no response is available for a request after <code>value</code> milliseconds, a <code>CORBA::NO_RESPONSE</code> exception is raised.

Table 4: *Orbacus policies*

Policy	Description
OB::RetryPolicy	<p>This policy is used to specify retry behavior after communication failures. Namely,</p> <ul style="list-style-type: none"> • the types of failures for which retries are allowed, • the time between successive retries, and • the maximum number of retries.
OB::TimeoutPolicy	<p>If an object has this policy and a connection cannot be established or no response is available for a request after <code>value</code> milliseconds, a <code>CORBA::NO_RESPONSE</code> exception is raised. If an object has <code>OB::ConnectTimeoutPolicy</code> or <code>OB::RequestTimeoutPolicy</code> set, those policies have precedence.</p>
OBPortableServer::InterceptorCall Policy	<p>This policy determines whether server-side interceptors will be called for requests on a POA. Server-side interceptors are enabled by default. To disable server-side interceptors for a POA, create the POA using this policy with a value of <code>false</code>.</p>
OBPortableServer::Communication sConcurrencyPolicy	<p>See “ooc.orb.oe.conc_model” on page 85 and “ooc.orb.poamanager.manager.conc_model” on page 87</p>
OBPortableServer::EndpointConfig urationPolicy	<p>See “ooc.orb.poamanager.manager.endpoint” on page 87</p>
OBPortableServer::GIOPVersionPol icy	<p>See “ooc.orb.poamanager.manager.version” on page 87</p>

Programming Examples

This section provides several examples of setting policies programmatically. Please note however that policies used to configure the ORB can easily be set at the ORB level, without requiring changes to the application, through the use of configuration properties. See “[ORB Properties](#)” on [page 78](#) for more information.

For the sake of clarity, the psuedo-code examples in this section lack exception handling.

In this section

This section contains the following examples:

Connection Reuse Policy	page 335
Retry Policy	page 338
Timeout Policy	page 340
Interceptor Call Policy	page 341
CommunicationsConcurrencyPolicy	page 343
EndpointConfigurationPolicy	page 345
GIOPVersionPolicy	page 347
Bidirectional Policy	page 349

Connection Reuse Policy

The following examples demonstrate how to set

`OB::ConnectionReusePolicy` at both the ORB level and the object level in C++ and Java. Setting a policy at the ORB level means that the ORB will honor this policy for all newly created objects. Existing objects maintain their current set of policies. Setting a policy at the object level overrides any ORB level policies applied to that object.

Setting the connection reuse policy to `false` at the ORB level means that the ORB will create a new connection from the client to the server for each new proxy object instead of reusing existing ones. Setting the connection reuse policy to `false` at the object level means that the client does not reuse connections to the server only for a particular proxy object.

If the connection reuse policy is set to `true` at some later point, communications channels that were previously created with a connection reuse policy set to `false` will not be reused. That is, the connection reuse policy is sticky, in the sense that the reuse policy that was in effect at the time that a communications channel is created stays with it. Setting the reuse policy at the object level means that for a client the ORB will not reuse the communications channel that is associated with the proxy object.

Connection Reuse Policy at ORB Level

Our first example shows how the connection reuse policy can be set at the ORB level. First in C++:

```

1 // C++
2 CORBA::Any boolAny;
3 boolAny <<= CORBA::Any::from_boolean(0);
4 CORBA::PolicyList policies;
5 policies.length(1);
6 policies[0] = orb -> create_policy(
7     OB::CONNECTION_REUSE_POLICY_ID, boolAny);
8 CORBA::Object_var pmObj =
9     orb -> resolve_initial_references("ORBPolicyManager");
10 CORBA::PolicyManager_var pm =
11     CORBA::PolicyManager::_narrow(pmObj);
12 pm -> set_policy_overrides(policies, CORBA::ADD_OVERRIDE);

```

Lines 2-3 Create an any and insert the value 0 (false).

Lines 4-5 Create a sequence containing one policy object.

Lines 6-7 Ask the ORB to create a connection reuse policy. Pass the any that contains the value for this policy.

Lines 8-10 Obtain the ORB level policy manager object.

Line 12 Add the policies to the ORB level policy manager.

And here is the same example in Java:

```
// Java
org.omg.CORBA.Any boolAny = orb.create_any();
boolAny.insert_boolean(false);
org.omg.CORBA.Policy[] policies = new org.omg.CORBA.Policy[1];
policies[0] = orb.create_policy(
    com.ooc.OB.CONNECTION_REUSE_POLICY_ID.value, boolAny);
org.omg.CORBA.PolicyManager pm =
    org.omg.CORBA.PolicyManagerHelper.narrow(
        orb.resolve_initial_references("ORBPolicyManager"));
pm.set_policy_overrides(policies,
    SetOverrideType.ADD_OVERRIDE);
```

This is equivalent to the C++ version.

Connection Reuse Policy at Object Level

And now the same example, but at the object level. C++ first:

```
// C++
CORBA::Any boolAny;
boolAny <<= CORBA::Any::from_boolean(0);
CORBA::PolicyList policies(1);
policies.length(1);
policies[0] = orb -> create_policy(
    OB::CONNECTION_REUSE_POLICY_ID,    boolAny);
CORBA::Object_var newObj =
    obj -> _set_policy_overrides(policies, CORBA::ADD_OVERRIDE);
```

This is the same as in the example for the ORB level.

Set the policy on the object by using the `_set_policy_overrides` method. This method returns a new object that has the set of policies applied.

And here is the same example in Java:

```
// Java
org.omg.CORBA.Any boolAny = orb.create_any();
boolAny.insert_boolean(false);
org.omg.CORBA.Policy[] policies = new org.omg.CORBA.Policy[1];
policies[0] =
    orb.create_policy(com.ooc.OB.CONNECTION_REUSE_POLICY_ID.value,
        boolAny);
org.omg.CORBA.Object newObj =
    obj._set_policy_override(policies,
        org.omg.CORBA.SetOverrideType.ADD_OVERRIDE);
```

This is equivalent to the C++ version.

Retry Policy

This example shows how to configure retries at the object level. The C++ version is presented first, followed by the Java version:

```
1 // C++
2 OB::RetryAttributes attrib;
3 attrib.mode = OB::RETRY_STRICT;
4 attrib.interval = 500;
5 attrib.max = 5;
6 attrib.remote = true;
7
8 CORBA::Any any;
9 any <<= attrib;
10 CORBA::PolicyList policies(1);
11 policies.length(1);
12 policies[0] = orb -> create_policy(OB::RETRY_POLICY_ID, any);
13 CORBA::Object_var newObj =
14     obj -> _set_policy_overrides(policies,
15     CORBA::ADD_OVERRIDE);
```

Line 3 Use the `RETRY_STRICT` mode, that is, retry only if the exception completion status is `COMPLETED_NO`.

Line 4 Wait 500 milliseconds between successive retries.

Line 5 Retry a maximum of 5 times.

Line 6 Allow retries on exceptions that are generated remotely (in addition to locally generated exceptions).

Lines 13-14 Set the policy on the object by using the `_set_policy_overrides` method. This method returns a new object that has the set of policies applied.

And now the same example in Java:

```
1 // Java
2 com.ooc.OB.RetryAttributes attrib =
3     new com.ooc.OB.RetryAttributes();
4 attrib.mode = com.ooc.OB.RETRY_STRICT.value;
5 attrib.interval = 500;
6 attrib.max = 5;
7 attrib.remote = true;
8
9 org.omg.CORBA.Any any = orb.create_any();
10 com.ooc.OB.RetryAttributesHelper.insert(any, attrib);
11 org.omg.CORBA.Policy[] policies = new
12     org.omg.CORBA.Policy[1];
13 policies[0] =
14     orb.create_policy(com.ooc.OB.RETRY_POLICY_ID.value, any);
15 org.omg.CORBA.Object newObj =
16     obj._set_policy_override(policies,
17         org.omg.CORBA.SetOverrideType.ADD_OVERRIDE);
```

This is equivalent to the C++ version.

Note that you can also set the retry policy at the ORB level.

Timeout Policy

This example shows how to configure timeouts at the object level. As usual, the C++ version is presented first, followed by the Java version:

```

1 // C++
2 CORBA::Any ULongAny;
3 ULongAny <<= (CORBA::ULong)1000;
4 CORBA::PolicyList policies(1);
5 policies.length(1);
6 policies[0] = orb -> create_policy(OB::TIMEOUT_POLICY_ID,
   ULongAny);
7 CORBA::Object_var newObj =
8     obj -> _set_policy_overrides(policies,
   CORBA::ADD_OVERRIDE);

```

Lines 2-6 We want to set the timeout to a value of 1000 milliseconds.

Lines 7-8 Set the policy on the object by using the `_set_policy_overrides` method. This method returns a new object that has the set of policies applied.

And now the same example in Java:

```

1 // Java
2 org.omg.CORBA.Any ULongAny = orb.create_any();
3 ULongAny.insert_ulong(1000);
4 org.omg.CORBA.Policy[] policies = new
   org.omg.CORBA.Policy[1];
5 policies[0] =
6     orb.create_policy(com.ooc.OB.TIMEOUT_POLICY_ID.value,
7         ULongAny);
8 org.omg.CORBA.Object newObj =
9     obj._set_policy_override(policies,
10    org.omg.CORBA.SetOverrideType.ADD_OVERRIDE);

```

This is equivalent to the C++ version.

Note that you can also set the timeout policy at the ORB level.

Interceptor Call Policy

This example shows how to create a new POA with server-side interceptors disabled. The C++ version is presented first, followed by the Java version:

```
1 // C++
2 CORBA::Object_var obj =
3     orb -> resolve_initial_references("RootPOA");
4 PortableServer::POA_var rootPOA =
5     PortableServer::POA::_narrow(obj);
6 PortableServer::POAManager_var manager =
7     rootPOA -> the_POAManager();
8
9 CORBA::Any any;
10 CORBA::PolicyList policies(1);
11 policies.length(1);
12 any <<= CORBA::Any::from_boolean(false);
13 policies[0] =
14     orb -> create_policy(
15         OBPortableServer::INTERCEPTOR_CALL_POLICY_ID, any);
16
17 PortableServer::POA_var myPOA =
18     rootPOA -> create_POA("MyPOA", manager, policies)
```

Lines 2-7 Obtain references to the root POA and its POA manager.

Lines 9-15 Create a policy set consisting of the `OBPortableServer::InterceptorCallPolicy` policy. The `OBPortableServer::InterceptorCallPolicy` policy is given a value of `false` so that server-side interceptors will be disabled.

Lines 17-18 Create a new POA using the policy set created above.

And now the same example in Java:

```
1 // Java
2 org.omg.CORBA.Object obj =
3 orb.resolve_initial_references("RootPOA");
4 org.omg.PortableServer.POA rootPOA =
5     org.omg.PortableServer.POAHelper.narrow(obj);
6 org.omg.PortableServer.POAManager manager =
7 rootPOA.the_POAManager();
8
9 org.omg.CORBA.Any any = orb.create_any();
10 org.omg.CORBA.Policy[] policies = new
11     org.omg.CORBA.Policy[1];
12 any.insert_boolean(false);
13 policies[0] = orb.create_policy(
14     com.ooc.OBPortableServer.INTERCEPTOR_CALL_POLICY_ID.value,
15     any);
16
17 org.omg.PortableServer.POA myPOA =
18     rootPOA.create_POA("MyPOA", manager, policies);
```

This is equivalent to the C++ version.

CommunicationsConcurrencyPolicy

This example shows how to create a new POA Manager with the concurrency model set to threaded. The C++ version is presented first, followed by the Java version.

```
1 // C++
2 CORBA::Object_var poaObj =
3     orb -> resolve_initial_references("RootPOA");
4 OBPortableServer::POA_var rootPOA =
5     OBPortableServer::POA::_narrow(poaObj);
6 POAManagerFactory_var factory = rootPOA ->
7     the_POAManagerFactory();
8 OBPortableServer::POAManagerFactory_var pmFactory =
9     OBPortableServer::POAManagerFactory::_narrow(factory);
10 POAManager_var myPOAManager;
11 PolicyList pl;
12 pl.length(1);
13 pl[0] = pmFactory ->
14     create_communications_concurrency_policy(
15         OBPortableServer::
16             COMMUNICATIONS_CONCURRENCY_POLICY_THREADED);
17 try
18 {
19     myPOAManager = create_POAManager("MyPOAManager", pl);
20 }
21 catch(const POAManagerFactory::ManagerAlreadyExists& ex)
22 {
23     // do something
24 }
```

And now the same example in Java:

```
1 // Java
2 org.omg.CORBA.Object obj =
3     orb.resolve_initial_references("RootPOA");
4 org.omg.PortableServer.POA rootPOA =
5     org.omg.PortableServer.POAHelper.narrow(obj)
6 org.omg.PortableServer.POAManagerFactory factory =
7     rootPOA.the_the_POAManagerFactory();
8 com.ooc.OBPortableServer.POAManagerFactory pmFactory =
9
10    com.ooc.OBPortableServer.POAManagerFactoryHelper.narrow(facto
11    ry);
12 org.omg.PortableServer.POAManager myPOAManager = null;
13 org.omg.CORBA.Policy[] pl = new Policy[1];
14 pl[0] = pmFactory.create_communications_concurrency_policy(
15
16    com.ooc.OBPortableServer.COMMUNICATIONS_CONCURRENCY_POLICY_TH
17    READED.value);
18
19 try
20 {
21     myPOAManager = pmFactory.create_POAManager("MyPOAManager",
22     pl);
23 }
24
25 catch(org.omg.PortableServer.POAManagerFactoryPackage.Manager
26 AlreadyExists ex)
27 {
28     // do something
29 }
30
31 catch(org.omg.CORBA.PolicyError ex)
32 {
33     // do something
34 }
```

EndpointConfigurationPolicy

This example shows how to create a new POA Manager with a list of endpoints for the Root POA Manager.

The C++ version is presented first, followed by the Java version:

```
1 // C++
2 CORBA::Object_var poaObj =
3     orb -> resolve_initial_references("RootPOA");
4 OBPortableServer::POA_var rootPOA =
5     OBPortableServer::POA::_narrow(poaObj);
6 POAManagerFactory_var factory = rootPOA ->
7     the_POAManagerFactory();
8 OBPortableServer::POAManagerFactory_var pmFactory =
9     OBPortableServer::POAManagerFactory::_narrow(factory);
10 POAManager_var myPOAManager;
11 PolicyList pl;
12 String_var config =
13     CORBA::string_dup("iiop --host localhost --port 5555
14     --bind localhost");
15 pl.length(1);
16 pl[0] = pmFactory ->
17     create_endpoint_configuration_policy(config.in());
18 try
19 {
20     myPOAManager = create_POAManager("MyPOAManager", pl);
21 }
22 catch(const POAManagerFactory::ManagerAlreadyExists& ex)
23 {
24     // do something
25 }
```

And now the same example in Java:

```
1 // Java
2 org.omg.CORBA.Object obj =
3     orb.resolve_initial_references("RootPOA");
4 org.omg.PortableServer.POA rootPOA =
5     org.omg.PortableServer.POAHelper.narrow(obj)
6 org.omg.PortableServer.POAManagerFactory factory =
7     rootPOA.the_the_POAManagerFactory();
8 com.ooc.OBPortableServer.POAManagerFactory pmFactory =
9
10    com.ooc.OBPortableServer.POAManagerFactoryHelper.narrow(facto
11    ry);
12 org.omg.PortableServer.POAManager myPOAManager = null;
13 org.omg.CORBA.Policy[] pl = new Policy[1];
14 String config = "iiop --host localhost --port 10999 --bind
15    localhost";
16 pl[0] =
17    pmFactory.create_endpoint_configuration_policy(config);
18 try
19 {
20     myPOAManager = pmFactory.create_POAManager("MyPOAManager",
21     pl);
22 }
23
24 catch(org.omg.PortableServer.POAManagerFactoryPackage.Manager
25    AlreadyExists ex)
26 {
27     // do something
28 }
29
30 catch(org.omg.CORBA.PolicyError ex)
31 {
32     // do something
33 }
```

GIOPVersionPolicy

This example shows how to create a new POA Manager with a specific GIOP version to be used in object references generated by that POA Manager.

This option is useful for backward compatibility with older ORBs that reject object references using a newer version of the protocol. In the example below the GIOP version is set to 1.2.

The C++ version is presented first, followed by the Java version:

```
1 // C++
2 CORBA::Object_var poaObj =
3     orb -> resolve_initial_references("RootPOA");
4 OBPortableServer::POA_var rootPOA =
5     OBPortableServer::POA::_narrow(poaObj);
6 POAManagerFactory_var factory = rootPOA ->
7     the_POAManagerFactory();
8 OBPortableServer::POAManagerFactory_var pmFactory =
9     OBPortableServer::POAManagerFactory::_narrow(factory);
10 POAManager_var myPOAManager;
11 PolicyList pl;
12 pl.length(1);
13 pl[0] = pmFactory -> create_giop_version_policy(
14     OBPortableServer::GIOP_VERSION_POLICY_1_2);
15 try
16 {
17     myPOAManager = create_POAManager("MyPOAManager", pl);
18 }
19 catch(const POAManagerFactory::ManagerAlreadyExists& ex)
20 {
21     // do something
22 }
```

And now the same example in Java:

```
1 // Java
2 org.omg.CORBA.Object obj =
3     orb.resolve_initial_references("RootPOA");
4 org.omg.PortableServer.POA rootPOA =
5     org.omg.PortableServer.POAHelper.narrow(obj)
6 org.omg.PortableServer.POAManagerFactory factory =
7     rootPOA.the_the_POAManagerFactory();
8 com.ooc.OBPortableServer.POAManagerFactory pmFactory =
9 com.ooc.OBPortableServer.POAManagerFactoryHelper.narrow
10    (factory);
11 org.omg.PortableServer.POAManager myPOAManager = null;
12 org.omg.CORBA.Policy[] pl = new Policy[1];
13 pl[0] = pmFactory.create_giop_version_policy(
14     com.ooc.OBPortableServer.GIOP_VERSION_POLICY_1_2.value);
15 try
16 {
17     myPOAManager = pmFactory.create_POAManager("MyPOAManager",
18         pl);
19 }
20 catch(org.omg.PortableServer.POAManagerFactoryPackage.Manager
21     AlreadyExists ex)
22 {
23     // do something
24 }
25 catch(org.omg.CORBA.PolicyError ex)
26 {
27     // do something
28 }
```

Bidirectional Policy

BidirectionalPolicy Server Implementation

This example shows how to create a new POA with the BidirectionalPolicy enabled to allow negotiation of Bidirectional connection reuse. The C++ example is presented first followed by the Java version:

```
1 // C++
2 CORBA::Object_var obj =
3     orb -> resolve_initial_references("RootPOA");
4 PortableServer::POA_var rootPOA =
5     PortableServer::POA::_narrow(obj);
6 PortableServer::POAManager_var manager =
7     rootPOA -> the_POAManager();
8
9 CORBA::Any any;
10 CORBA::PolicyList policies(1);
11 policies.length(1);
12 any <= BiDirPolicy::BOTH;
13 policies[0] = orb -> create_policy(
14     BiDirPolicy::BIDIRECTIONAL_POLICY_TYPE, any);
15
16 PortableServer::POA_var myPOA =
17     rootPOA -> create_POA("MyPOA", manager, policies)
```

Lines 2-7 Obtain the reference to the RootPOA and RootPOAManager

Lines 9-14 Create a new BidirectionalPolicy containing the value of BiDirPolicy::BOTH (to enable Bidirectional connection reuse negotiation).

Lines 16-17 Create the new POA with this policy to enable BiDir negotiation on requests destined for this POA.

And now the same example in Java:

```

1 // Java
2 org.omg.CORBA.Object obj =
3   orb.resolve_initial_references("RootPOA");
4 org.omg.PortableServer.POA rootPOA =
5   org.omg.PortableServer.POAHelper.narrow(obj);
6 org.omg.PortableServer.POAManager manager =
7   rootPOA.the_POAManager();
8
9 org.omg.CORBA.Any any = orb.create_any();
10 org.omg.CORBA.Policy[] policies = new
11   org.omg.CORBA.Policy[1];
12 org.omg.BiDirPolicy.BidirectionalPolicyValueHelper.insert(
13   any, org.omg.BiDirPolicy.BOTH.value);
14 policies[0] = orb.create_policy(
15   org.omg.BiDirPolicy.BIDIRECTIONAL_POLICY_TYPE.value,
16   any);
17 org.omg.PortableServer.POA myPOA =
18   rootPOA.create_POA("MyPOA", manager, policies);

```

This is equivalent to the C++ version.

BidirectionalPolicy Client Implementation

This example shows how to create an object reference with the BidirectionalPolicy enabled to signal connection reuse is allowed over connections established with this object reference. The C++ example is presented first followed by the Java version:

```

1 // C++
2 CORBA::Object_var obj =
3   orb -> string_to_object("refile:/Hello.ref");
4
5 CORBA::PolicyList policies(1);
6 policies.length(1);
7 CORBA::Any any;
8 any <<= BiDirPolicy::BOTH;
9 policies[0] = orb -> create_policy(
10   BiDirPolicy::BIDIRECTIONAL_POLICY_TYPE,
11   any);
12
13 obj = obj -> _set_policy_overrides(
14   policies, CORBA::ADD_OVERRIDE);
15
16 Hello_var hello = Hello::_narrow(obj);

```

Lines 2-3 Obtain the object reference from some means (here using a file)

Lines 5-11 Create the BidirectionalPolicy with a value of BOTH to enable BiDir.

Lines 13-14 Add the Bidirectional Policy to the object and make sure to catch the return object reference.

Line 16 Narrow the object to the specific type for method invocation.

And now the Java version:

```
1 // Java
2 org.omg.CORBA.Object obj =
3     orb.string_to_object("refile:/Hello.ref");
4
5 org.omg.CORBA.Any any = orb.create_any();
6 org.omg.BiDirPolicy.BidirectionalPolicyValueHelper.
7     insert(any, org.omg.BiDirPolicy.BOTH.value);
8 org.omg.CORBA.Policy[] policies =
9     new org.omg.CORBA.Policy[1];
10 policies[0] = orb.create_policy(
11     org.omg.BiDirPolicy.BIDIRECTIONAL_POLICY_TYPE.value, any);
12
13 obj = obj._set_policy_override(policies,
14     org.omg.CORBA.SetOverrideType.ADD_OVERRIDE);
15
16 Hello hello = HelloHelper.narrow(obj);
```

This is equivalent to the C++ version.

Asynchronous Method Invocation

This chapter describes how to design asynchronous non-blocking clients.

In this chapter

This chapter contains the following sections:

Introduction	page 354
AMI Router	page 355
Router Usage	page 356
Router Administration Properties	page 357
AMI Reply Handler Implementation	page 359
AMI Poller Implementation	page 363
Configuring Clients and Servers	page 365

Introduction

Overview

Asynchronous Method Invocation (AMI) allows the design of asynchronous, non-blocking clients without change to server-side design. This allows a client to invoke a request on a server and immediately return, without waiting for the request to be serviced. The response will be delivered to the client at a later time through either a callback mechanism, initiated by the ORB (AMI Reply Handler implementation), or a polling mechanism, initiated by the client (AMI Polling implementation).

The Orbacus 4.3 AMI implementation is based on OMG's CORBA 3.0.2 specification (specifically Chapter 22: CORBA Messaging; Section II: Messaging Programming Model.) for the client-side code generation, while the message delivery is done through an AMI Router. Quality of Service (QoS) policies are not currently supported, though they will be incorporated into a future release of the product when the routing capability is enhanced.

The AMI-enabled client code is generated by using the `--with-async` option for the Orbacus code generators. Also, the target IDL file must include the `AMI.idl` file.

Modifying an application's client code to use AMI is discussed in the following sections. The AMI "echo" demos, located in the directory `ob/demo/AMI/`, will be used as the basis for this discussion.

In this section

This section contains the following topics:

AMI Router	page 355
Router Usage	page 356
Router Administration Properties	page 357
AMI Reply Handler Implementation	page 359
AMI Poller Implementation	page 363
Configuring Clients and Servers	page 365

AMI Router

The AMI Router allows users to configure their systems so that servers that have the potential to go offline on a regular basis can have an associated set of AMI Routers specified as an alternative, fallback destination for their requests. Rather than encumbering the client application with retry logic, the AMI Router allows the client application to send a message as though the server were available, and continue processing. The message will actually be delivered to a router that can then worry about delivering the message to the server when it becomes available. The client application can then handle the expected response from the asynchronous invocation when necessary.

Router Usage

The AMI Router is currently implemented using Orbacus for C++, but can be used with C++ and Java clients and servers. Command-line usage is as follows:

```
amirouter
  [-h,--help] [-v,--version] [-i,--ior]
  [-p,--persistent] [-w,--workers WORKERS]
```

Options

-h --help	Display the command-line options supported by the router.
-v --version	Display the version of the router.
-i --ior	Prints the stringified IOR of the router to standard output.
-p --persistent	Starts a persistent request router for use with the AMI polling model.
-w --workers WORKERS	Sets the number of worker threads for processing requests. The value of WORKERS should be between 1 and 255.

Router Administration Properties

In addition to the standard configuration properties described in Chapter 4, the Orbacus AMI Router also supports the following properties for configuring router administration functionality:

ooc.router.retry_policy

Values: `immediate_suspend`, `unlimited_ping`, `limited_ping`

Default: `unlimited_ping`

Specifies the retry policy to use for the router. If a router has a retry policy of `immediate_suspend`, its state is set to `SUSPENDED` as soon as a message fails to be delivered to it. Otherwise, retry attempts are governed by additional configuration parameters, given below.

ooc.router.retry_policy.base_interval

Value: Integer $n > 0$

Default: 5

This is the base number of seconds to wait between retry attempts. This property is used for both the `unlimited_ping` and the `limited_ping` retry policies.

ooc.router.retry_policy.backoff_factor

Value: Decimal $n > 0$

Default: 2

The time between retry attempts is the product of the value of the `base_interval` multiplied by the value of the `backoff_factor`. After the first retry attempt, which is based solely on the base interval, each subsequent retry is multiplied by the `backoff_factor`. This property is used for both the `unlimited_ping` and the `limited_ping` retry policies.

ooc.router.retry_policy.max_backoffs

Value: Integer $n > 0$

Default: 6

The maximum number of times the backoff factor is applied to the base retry interval. This property is used for both the `unlimited_ping` and the `limited_ping` retry policies.

ooc.router.retry_policy.interval_limit

Value: Integer $n > 0$

The maximum number of retry attempts made. This property is used for `limited_ping` retry policy only.

ooc.router.decay_policy.decay_seconds

Value: Integer $n \geq 0$

Default: 0

The time (in seconds) for which a destination registration is valid. If this is set to zero (0), the registration remains valid until the destination explicitly unregisters itself with a call to `unregister_destination`.

ooc.router.resume_policy.resume_seconds

Value: Integer $n \geq 0$

Default: 1200 (20 minutes)

The time (in seconds) after which a suspended destination should be resumed. If this is set to zero (0), the registered destination can only be resumed with an explicit call to `resume_destination`.

Note: Orbacus 4.3.1 does not allow this value to be set to zero (0). This is required due to the lack of persistence in the AMI Router in the 4.3.1 version of Orbacus.

AMI Reply Handler Implementation

In the reply handler implementation, the user must instantiate a callback object and pass it to the ORB in the deferred AMI request (or `sendc_call`). The ORB can then use this callback object to inform the client application that the request has completed. This callback object must be derived from the generated `AMI_EchoHandler` class. This is shown in the C++ and Java code examples that follow.

C++

The following code snippet shows the client application making the AMI deferred call for the Reply Handler implementation. The `EchoHandler_impl` class must be implemented by the user. For a complete example, please see the code in the `ob/demo/AMI/echo_reply_router/` directory of the Orbcus for C++ distribution.

```

1  CORBA::PolicyList policies;
2  policies.length(2);
3  policies[0] = rootPOA ->
   create_id_assignment_policy(PortableServer::USER_ID);
4  policies[1] = rootPOA ->
   create_lifespan_policy(PortableServer::PERSISTENT);
5  PortableServer::POA_var handlerPOA =
   rootPOA -> create_POA("myHandlerPOA", manager, policies);
6  CORBA::Object_var obj = orb -> string_to_object("relfile:/
   Echo.ref");
7  Echo_var echo = Echo::_narrow(obj);
8  EchoHandler_impl* handler = new EchoHandler_impl(handlerPOA);
9  PortableServer::ServantBase_var servant = handler;
10 PortableServer::ObjectId_var id =
   PortableServer::string_to_ObjectId("myHandlerServant");
11 handlerPOA -> activate_object_with_id(id, servant);
12 AMI_EchoHandler_var handlerRef = handler -> _this();

13 echo -> sendc_echo_message(handlerRef, "Hello");

14 while(handler -> receptions() < 1)
15 orb -> perform_work();

```

Lines 1-5 Create a persistent POA for the reply handler. This is important as it allows the router to deliver the reply in the event that the client goes down and comes back up. Servers should also use persistent POAs for the same reason.

Lines 6-7 Create the `Echo` object based on the IOR in the `Echo.ref` file.

Lines 8-12 Instantiate a new `EchoHandler_impl` object using the new persistent POA. This class must be created by the user and derived from the generated `POA_AMI_EchoHandler`. Sample code for an `EchoHandler_impl` can be found in the `Echo_impl.cpp` file located in the `ob/demo/AMI/ech_reply_router/ demo` folder.

Line 13 Make the deferred call, passing the handler as the first parameter.

Lines 14-15 Wait for the response to come back. This is simply how this demo was implemented. How the callback is handled is application dependent.

Java

The following code snippet shows the client application making the AMI deferred call for the Reply Handler implementation. The `AsyncEchoHandler` class must be implemented by the user. For a complete example, please see the code in the `ob/demo/AMI/echo_reply_router/` directory of the Orbacus for Java distribution.

```
1  org.omg.PortableServer.POA rootPOA =
    org.omg.PortableServer.POAHelper.narrow(
    orb.resolve_initial_references("RootPOA"));
2  org.omg.PortableServer.POAManager manager =
    rootPOA.the_POAManager();

3  org.omg.PortableServer.POA persistentPOA = null;
4  try
    {
5  org.omg.CORBA.Policy[] policies = new
    org.omg.CORBA.Policy[2];
6  policies[0] = rootPOA.create_lifespan_policy(
    org.omg.PortableServer.LifespanPolicyValue.PERSISTENT);
7  policies[1] = rootPOA.create_id_assignment_policy(
    org.omg.PortableServer.IdAssignmentPolicyValue.USER_ID);
8  persistentPOA = rootPOA.create_POA("PersistentPOA", manager,
    policies);
    }
9  catch (org.omg.PortableServer.POAPackage.AdapterAlreadyExists
    ex)
    {
10     ex.printStackTrace();
11     throw new RuntimeException();
    }
12  catch (org.omg.PortableServer.POAPackage.InvalidPolicy ex)
    {
13     ex.printStackTrace();
14     throw new RuntimeException();
    }

15  AsyncEchoHandler asyncHandler = new
    AsyncEchoHandler(rootPOA);
16  echo.AMI_EchoHandler handler = asyncHandler._this(orb);

17  org.omg.CORBA.Object obj = orb.string_to_object("relfile:/
    Echo.ref");
18  echo.Echo ec = echo.EchoHelper.narrow(obj);

19  ec.sendc_echo_message(handler, "Hello");
```

Lines 1-14 Create a persistent POA for the reply handler. This is important as it allows the router to deliver the reply in the event that the client goes down and comes back up. Servers should also use persistent POAs for the same reason.

Lines 15-16 Instantiate a new `AsyncEchoHandler` object using our new persistent POA. This class must be created by the user and derived from the generated `AMI_EchoHandlerPOA`. Sample code for an `AsyncEchoHandler` can be found in the `AsyncEchoHandler.java` file located in the `ob/demo/AMI/echo_reply_router/` demo folder.

Lines 17-18 Create the `Echo` object based on the IOR in the `Echo.ref` file.

Line 19 Make the deferred call, passing the handler as the first parameter.

AMI Poller Implementation

Overview

In the poller implementation, the user is returned a poller object from the deferred AMI request (or `sendp_` call). The user can then query this poller object to find out when a request has completed. This is shown in the C++ and Java code examples that follow.

C++

For complete code, please see the `EchoClient.cpp` file in the `ob/demo/AMI/echo_poll_router/` directory of the Orbacus for C++ distribution.

```
1  CORBA::Object_var obj = orb -> string_to_object("relfile:/
Echo.ref");
2  Echo_var echo = Echo::_narrow(obj);
3  AMI_EchoPoller_var poller = echo ->
sendp_echo_message(L"Hello!");
4  CORBA::WString_var reply;
5  CORBA::ULong max_timeout = (CORBA::ULong)-1;
6  poller -> echo_message(max_timeout, reply);
```

Lines 1-2 Create the Echo object based on the IOR in the `Echo.ref` file

Line 3 Make the deferred call, which returns an `AMI_EchoPoller` object based on the generated class. Note that the user does not have to override this class, as must be done for the Reply Handler implementation.

Lines 4-5 Set up the parameters that will be passed to the poller function.

Line 6 Check the poller for the status of the deferred call. This function will update any parameters with data that was expected from the deferred call. Note that a timeout value of "-1" will cause the client code to wait forever.

Java

For complete code, please see the `EchoClient.java` file in the `ob/demo/AMI/echo_poll_router/` directory of the Orbacus for Java distribution.

```
1  org.omg.CORBA.Object obj = orb.string_to_object("refile:/
   Echo.ref");
2  echo.Echo ec = echo.EchoHelper.narrow(obj);
3  echo.AMI_EchoPoller poller =
   ec.sendp_echo_message("Hello!");
4  org.omg.CORBA.StringHolder reply = new
   org.omg.CORBA.StringHolder();
5  poller.echo_message(-1, reply);
```

Lines 1-2 Create the Echo object based on the IOR in the `Echo.ref` file.

Line 3 Make the deferred call, which returns an `AMI_EchoPoller` object based on the generated class. Note that the user does not have to override this class, as must be done for the Reply Handler implementation.

Line 4 Set up the parameters that will be passed to the poller function.

Line 5 Check the poller for the status of the deferred call. This function will update any parameters with data that was expected from the deferred call. Note that a timeout value of `-1` will cause the client code to wait forever.

Configuring Clients and Servers

Configuring router lists

Clients and servers can specify any routers they want to use for the routing of requests and replies to them via the configuration file property `ooc.ami.router.#`, where # is a unique integer that differentiates the router from other routers in the list. When the list of router property keys is sorted in increasing order, which is done automatically by the client or server, routers that appear later in the list are given preference when routing request/replies over routers that appear earlier in the list.

The value for the `ooc.ami.router` property is a string that represents an object reference or location to be used for contacting the router. These can be specified in one of the following four formats:

1. An object reference file (for example, `router1.ref`)

```
ooc.ami.router.1=relfile:/router1.ref
```

2. A stringified IOR object reference

```
ooc.ami.router.2=IOR:013074b70d00000049444c3a4563686f3a3...
```

3. A corbaloc address

```
ooc.ami.router.3=corbaloc::localhost:20000/AMIRouter
```

The Orbacus AMI router uses the stringified object key `AMIRouter`.

4. A host/port combination in the format `<host>:<port>`

```
ooc.ami.router.4=localhost:20000
```

Note: Using corbalocs or host/port combinations limits the functionality of the router administration, as these methods provide incomplete object references that prevent the router administration from doing proper object comparisons.

Sample configuration file

The following is a sample configuration file that specifies the endpoint for the application along with three routers that can be used for routing request/replies:

```
#
# Persistent handlers require a persistent port
#
ooc.orb.ia.endpoint=iiop --port 20000

#
# List of routers to use for routing requests
#
ooc.ami.router.1=relfile:/router1.ref
ooc.ami.router.2=relfile:/router2.ref
ooc.ami.router.3=corbaloc::localhost:30000/AMIRouter
```

This configuration file defines three routers for routing request/replies to an application using the file, with router 3 given first preference, then router 2, and finally router 1.

Applications using AMI polling model

Applications using the AMI polling model should start a single persistent AMI request router instead of the usual list of routers. This can be done through the configuration property `ooc.ami.persistent_router` and is placed in the configuration for the application making the polling requests. The value for this property is again a string that represents an object reference or location to be used for contacting the router. These object references or locations can be specified using one of the four methods listed for the `ooc.ami.router` configuration property. For example:

```
#
# AMI Persistent Router
#
ooc.ami.persistent_router=relfile:/p_router.ref
```

Application development considerations

Applications that can potentially receive requests or, in the case of applications using the AMI callback model, replies from AMI routers should be implemented using persistent POAs. This allows routers to deliver requests and/or replies in the event that an application is terminated and

restarted at a later time. Applications that do not use persistent POAs will generate a different object reference when restarted and the router will be unable to deliver the request and/or reply.

Concurrency Models

This chapter describes how an Object Request Broker handles communication and request execution using single- and multi-threaded concurrency models.

In this chapter

This chapter contains the following sections:

Concurrency Models	page 370
Single-Threaded Concurrency Model	page 372
Multi-Threaded Concurrency Models	page 375
The Reactor	page 382

Concurrency Models

What is a Concurrency Model?

A concurrency model describes how an Object Request Broker (ORB) handles communication and request execution. There are two main categories of concurrency models, single-threaded concurrency models and multi-threaded concurrency models.

Single-threaded concurrency models describe how an ORB behaves while a request is sent or received in a single-threaded environment. For example, one model is to simply let the ORB block while sending and receiving messages. Another model is to let the ORB do some work while sending and receiving messages, for example to receive user input through a keyboard or a GUI, or to simply transfer buffered messages.

Multi-threaded concurrency models describe how the ORB makes use of multiple threads, for example to send and receive messages in the background. Multi-threaded concurrency models also describe how several threads can be active in the user code and the strategy the ORB employs to create these threads.

Why different Concurrency Models?

There is no one size fits all approach with respect to concurrency models. Each concurrency model provides a unique set of properties, each having advantages and disadvantages. For example, applications using callbacks must have a concurrency model that allows nested method invocations to avoid deadlocks. Other applications must be optimized for speed, in which case a concurrency model with the least overhead will be chosen.

Some ORBs are highly specialized, providing only the most frequently used concurrency models for a specific domain. Orbacus takes a different approach by supporting several concurrency models.

Orbacus Concurrency Models Overview

Orbacus allows different concurrency models to be established for the client and server activities of an application. The client-side concurrency models are *Reactive* and *Threaded*. The server-side concurrency models are *Reactive*, *Threaded*, *Thread-per-Client*, *Thread-per-Request* and *Thread Pool*.

Selecting Concurrency Models

Concurrency models can be selected either by properties or command-line parameters (see [Chapter 4](#)). The default concurrency models are shown in [Table 5](#).

Table 5: *Default Concurrency Models*


	Client	Server
Java	Threaded	Threaded
C++	Threaded	Reactive

Single-Threaded Concurrency Model

Orbacus supports one single-threaded concurrency model: *reactive*.

Reactive servers use calls to operations like `select` in order to simultaneously accept incoming connection requests, to receive requests from multiple clients and to send back replies. This is shown in [Figure 9](#).

Figure 9: *Reactive Server*



Reactive clients also use operations like `select` to avoid blocking. This means that while a request to a server is sent or a reply from that server is received, the client can simultaneously send buffered requests to other servers or receive and buffer replies.


This is very useful for oneway operations or the Dynamic Invocation Interface (DII) operation `send_deferred` in combination with `get_response` or `poll_response`.

Note: For more information on `send_deferred`, `get_response` and `poll_response`, see the chapter “The Dynamic Invocation Interface” in [4].

However, the main advantage of a reactive client becomes apparent if it is used together with a reactive server in mixed client/server applications. A mixed client/server application is a program that is both a client and server at the same time. Without the reactive concurrency model it is not possible to use nested method calls in single-threaded applications, which are absolutely necessary for most kinds of callbacks.

Consider two programs A and B, both mixed client/server applications. First A tries to call a method f on B. Before this method returns, B calls back A by invoking method g . This scenario is quite common, and for example is used in the popular Model-View-Controller pattern [1]. Using the reactive concurrency model for the client, A can dispatch incoming requests while waiting for B's reply for f . This is shown in Figure 10.

Figure 10: *Reactive Client/Server*



The reactive concurrency models are also very fast. There is no overhead for thread creation or context switching. Only an additional call to an operation like `select` is needed before operations such as `send`, `recv` or `accept` can be used by the ORB.

Note: Instead of directly using operations like `select`, Orbacus uses a Reactor to provide for flexible integration with existing event loops and to allow the installation of user supplied event handlers. See [“The Reactor” on page 382](#) for more information.

The maximum nesting level for the reactive concurrency model is usually much higher than for threaded concurrency models. The reason is that the maximum nesting level for threaded models is determined by the maximum number of threads allowed per process, whereas the reactive concurrency model is only limited by the maximum stack size per process.

Multi-Threaded Concurrency Models

In this section

This section covers the following concurrency models:


Threaded Clients and Servers	page 376
Thread-per-Client Server	page 378
Thread-per-Request Server	page 379
Thread Pool Server	page 380
Leader_Follower	page 381

Threaded Clients and Servers

For a threaded client, outgoing requests are sent by the user thread, but a separate receiver thread for handling replies is allocated for each connection to a server. The separate receiver thread allows messages to be received and buffered for later retrieval by the user thread with DII operations such as `get_response` or `poll_response`.

Like a threaded client, a threaded server uses a separate thread for receiving requests from clients, but sends replies in the dispatch thread. Additionally, there is a separate thread dedicated to accepting incoming connection requests, so that a threaded server can serve more than one client at a time. Orbacus's threaded server concurrency model allows only one active thread in the user code. This means that even though many requests can be received simultaneously, the execution of these requests is serialized. This is shown in [Figure 11](#). (For simplicity, the dispatch arrows and the corresponding return arrows are omitted in this and all following diagrams.)

Figure 11: *Threaded Server*



In the example, the threaded server has two clients connected to it and thus two receiver threads. First A calls `f` on the server. If, before `f` returns, B tries to call another operation `g`, this request is delayed until `f` returns. The same is true for A's call to `h`, which must wait until `g` returns.


Allowing only one active thread in user code has the advantage of the user code not having to take care of any kind of thread synchronization. This means that the user code can be written as if for a single threaded system, but without losing the advantage of the ORB optimizing its operation by using multiple threads internally.

The threaded concurrency model is still fast. No calls to operations like `select` are required. Time consuming thread creation is only necessary when a new client is connecting, but not for each request. However, thread context switching makes this approach slower than the reactive concurrency model, at least on a single-processor computer.

Thread-per-Client Server

The thread-per-client server concurrency model is very similar to the threaded server concurrency model, except that the ORB allows one active thread-per-client in the user code. This is shown in [Figure 12](#).

Figure 12: *Thread-per-Client Server*




A's call to f and B's call to g are carried out simultaneously, each in its own thread. However, if A tries to call another operation h (for example by sending requests from different threads in a multi-threaded client or by using the DII operation `send_deferred` in a single-threaded client) as long as f has not finished yet, the execution of h is delayed until f returns.

The thread-per-client model is still efficient. Like with the threaded concurrency model, no threads need to be created, except when new connections are accepted.

Thread-per-Request Server

If the thread-per-request server concurrency model is chosen, the ORB creates a new thread for each request. This is shown in [Figure 13](#).

Figure 13: *Thread-per-Request Server*



(For simplicity there are no separate arrows for dispatch and thread creation in the diagram.) With the thread-per-request model, requests are never delayed. When they arrive, a new thread is created and the request is executed in the user code using this thread. On return, the thread is destroyed.


Besides using a reactive client together with a reactive server, the thread-per-request server in combination with a threaded client is the only other model that allows nested method calls with an unlimited nesting level. The thread pool model also allows nested method calls, but the nesting level is limited by the number of threads in the pool.

The thread-per-request concurrency model is inefficient. The main problem results from the overhead involved in creating new threads, namely one for each request.

Thread Pool Server

The thread pool model uses threads from a pool to carry out requests, so that threads have to be created only once and can then be reused for other requests. Figure 14 shows an example with one client and a thread pool server with three threads in the pool. (Sender and receiver threads are not shown.)

Figure 14: *Thread Pool Server*



The first three operation calls f , g and h can be carried out immediately, since there are three threads in the pool. However, the fourth request i is delayed until at least one of the other requests returns.

Since there is no time-consuming thread creation, the thread pool concurrency model performs better than the thread-per-request model. The thread pool is a good trade-off if on the one hand frequent thread creation and destruction result in unacceptable performance, but on the other hand delaying the execution of concurrent method calls is also not desired.

Leader_Follower

In the Leader-Follower concurrency model, each thread from the thread pool will transition between the following states:

- leader
- processing
- follower

The leader thread, of which there can only be one at any given time, waits for incoming requests. When a request is received, the leader thread will promote a new leader while it goes into the processing state to handle the received requests. Once processing is complete, the thread is absorbed back into the pool, where it waits to be promoted again. While in the waiting state, the thread is said to be a follower.

In this model, it is possible to have multiple threads in the processing state at the same time. However, as stated above, there can only ever be one leader.

The main advantage of this model is scalability. It allows tight control over the number of threads used by each POAManager.

The Reactor

What is a Reactor?

In reactive mode (see [“Single-Threaded Concurrency Model” on page 372](#)), Orbacus uses a so-called *Reactor* for event dispatching [11]. Simply speaking, the Reactor is an instance in Orbacus (a singleton) where special objects — so-called event handlers — can register if they are interested in specific events. These events can be network events, such as an event signaling that data are ready to be read from a network connection.

Again, this chapter only applies to Orbacus when used with reactive concurrency models. If you use Orbacus with any other concurrency model, for example any of the multi-threaded models, the following examples are not applicable. Also, since Orbacus for Java currently doesn't support the reactive model at all, the following only applies to Orbacus for C++.

Available Reactors

Currently there are three Reactors supported by Orbacus:

- The standard select Reactor which relies on the Berkeley Sockets `select` function.
- A special Reactor for use with the X11 Window System. This Reactor handles X11 events (which for example can trigger X11 callbacks) and CORBA network events simultaneously. See [“The X11 Reactor” on page 383](#).
- A special Reactor for use with Microsoft Windows 95/98/NT/2000. This Reactor handles Windows messages and CORBA network events simultaneously. See [“The Windows Reactor” on page 385](#).

The default Reactor is the select Reactor. If one of the other Reactors is to be used, it must be initialized explicitly.

The X11 Reactor

An application that wants to use the X11 Reactor can obtain a special X11 Reactor using `OB::GetX11Reactor()`, which it must pass to

`OBCORBA::ORB_init()`:

```
1 // C++
2 #include <X11/Intrinsic.h>
3
4 #include <OB/CORBA.h>
5 #include <OB/Logger.h>
6 #include <OB/Properties.h>
7 #include <OB/X11.h>
8
9 int main(int argc, char* argv[])
10 {
11     XtAppContext appContext;
12     Widget topLevel = XtAppInitialize(&appContext,
13     "MyApplication", 0, 0, &argc, argv, 0, 0, 0);
14
15     OB::Reactor_var reactor = OB::GetX11Reactor(appContext);
16
17     CORBA::ORB_var = OBCORBA::ORB_init(argc, argv,
18     OB::Properties::_nil(), OB::Logger::_nil(), reactor);
19
20     ... // POA initialization not shown
21
22     orb -> run();
23
24     ... // Cleanup not shown
25 }
```

Lines 1-7 Include header files.

Lines 11-13 Initialize the X11 application.

Line 15 Use the X11 application context to obtain a X11 Reactor.

Line 17 Initialize the ORB using the Orbacus-specific `OBCORBA::ORB_init()`.

Line 22 Enter the CORBA event loop. This loop will also dispatch X11 events. Alternatively, the standard X11 event loop may be called, which will also dispatch CORBA events.

The Windows Reactor

Using a Windows Reactor is very similar to using a X11 Reactor:

```
1 // C++
2 #include <Windows.h>
3
4 #include <OB/CORBA.h>
5 #include <OB/Logger.h>
6 #include <OB/Properties.h>
7 #include <OB/OBWindows.h>
8
9 int main(int argc, char* argv[])
10 {
11     HINSTANCE hInstance = GetModuleHandle(0);
12
13     OB::Reactor_var reactor = OB::GetWindowsReactor(hInstance);
14
15     CORBA::ORB_var = OBCORBA::ORB_init(argc, argv,
16         OB::Properties::_nil(), OB::Logger::_nil(), reactor);
17
18     ... // POA initialization not shown
19
20     orb -> run();
21
22     ... // Cleanup not shown
23 }
```

Lines 2-7 Include header files.

Line 13 Use the Windows application instance to get a Windows Reactor.

Lines 15-16 Initialize the ORB using the Orbacus-specific

`OBCORBA::ORB_init()`.

Line 20 Enter the CORBA event loop, which now also dispatches Windows events. The standard Windows event loop may also be called, which will then also dispatch CORBA events.

The Open Communications Interface

The Open Communications Interface (OCI) defines common interfaces for pluggable protocols. TCP/IP is one possible candidate for an OCI plug-in. Since Orbacus uses GIOP, such a plug-in then implements the IIOPI protocol. Other candidates are SCCP (Signaling Connection Control Part, part of SS.7) or SAAL (Signaling ATM Adaptation Layer).

In this chapter

This chapter contains the following sections:

Interface Summary	page 388
OCI Reference	page 391
The IIOPI OCI Plug-in	page 399
The UDP OCI Plug-in	page 404
The Bi-directional OCI Plug-in	page 413

Interface Summary

Buffer

An interface for a buffer. A buffer can be viewed as an object holding an array of octets and a position counter, which determines how many octets have already been sent or received.

Transport

The Transport interface allows the sending and receiving of octet streams in the form of Buffer objects. There are blocking and non-blocking send/receive operations available, as well as operations that handle time-outs and detection of connection loss.

Acceptor and Connector

Acceptors and Connectors are Factories [2] for Transport objects. A Connector is used to connect clients to servers. An Acceptor is used by a server to accept client connection requests.

Acceptors and Connectors also provide operations to manage protocol-specific IOR profiles. This includes operations for comparing profiles, adding profiles to IORs or extracting object keys from profiles.

Acceptor and Connector Factories

Acceptor and Connector Factories are used by clients to create Acceptors and Connectors. Acceptors are created infrequently, usually only when POA Managers are created. Connectors, however, need to be created by clients whenever a new connection to a server has to be established.

The only component of the OCI that is configurable by applications is the Acceptor. When creating a new Acceptor, an Acceptor Factory takes a sequence of protocol-specific parameters which are used to configure the Acceptor. Each plug-in implementation should document these configuration parameters. The configuration parameters for the plug-ins included with Orbacus are described later in this chapter.

The Registries

The ORB provides Acceptor and Connector Factory Registries. These registries allow the plugging-in of new protocols. Transport, Connector, Connector Factory, Acceptor Factory and Acceptor must be written by the

plug-in implementers. The Connector Factory must then be registered with the ORB's Connector Factory Registry and the Acceptor Factory must be registered with the ORB's Acceptor Factory Registry.


The Info Objects

Info objects provide information on Transports, Acceptors and Connectors. A Transport Info provides information on a Transport, an Acceptor Info on an Acceptor and a Connector Info on a Connector. To get information for a concrete protocol, these info objects must be narrow'd to an info object for this protocol, for example, in the case of an IIOP plug-in, a `OCI::TransportInfo` must be narrow'd to `OCI::IIOP::TransportInfo`.

Class Diagram

Figure 15 shows the classes and interfaces of the OCI (except for the Buffer and Info interfaces).

Figure 15: OCI Class Diagram



Orbacus provides abstract base classes for the interfaces Connector Factory, Connector, Transport, Acceptor Factory and Acceptor. The protocol plug-in must inherit from these classes in order to provide concrete implementations for a specific protocol. Orbacus also provides concrete classes for the interfaces Buffer, Connector Factory Registry and Acceptor Factory Registry. Instances of Connector Factory Registry and Acceptor Factory Registry can be obtained via the ORB operation `resolve_initial_references`, using the identifiers `OCIconFactoryRegistry` and `OCIAccFactoryRegistry`, respectively. Concrete implementations of Connector Factory must be registered with the Connector Factory Registry, and concrete implementations of Acceptor Factory must be registered with the Acceptor Factory Registry.

OCI Reference

This chapter does not contain a complete reference of the OCI. It only explains OCI basics and, in the remainder of this chapter, how it is used from the application programmer's point of view for the most common tasks. For more information on how to use the OCI to write your own protocol plug-ins, and for a complete reference, please refer to [Appendix E](#).

OCI for the Application Programmer

The following sections only apply to the standard Orbacus IIOP plug-in. For other plug-ins, please refer to the plug-in's documentation.

A Converter Class for Java	page 392
Getting Hostnames and Port Numbers	page 393
Determining a Server's IP Address	page 397

A Converter Class for Java

As you will see in the following examples, the OCI info objects return port numbers as IDL `unsigned short` values and IP addresses as an array of 4 IDL `unsigned octet` values. This works fine for C++, but in Java this causes a problem, because there are no unsigned types in Java. The Java mapping simply maps unsigned types to signed types. Consider for example the IP address 126.127.128.129. In Java, the OCI will return this as 126.127.-128.-127, because 128 and 129, if bit-wise mapped to the Java `byte` type, are -128 and -127.

To avoid this problem, we will use a helper class which converts port numbers and IP addresses to Java `int` types. This helper class looks as follows:

```
1 // Java
2 final class Converter
3 {
4     static int port(short s)
5     {
6         if(s < 0)
7             return 0xffff + (int)s + 1;
8         else
9             return (int)s;
10    }
11
12    static int[] addr(byte[] bArray)
13    {
14        int[] iArray = new int[4];
15        for(int i = 0 ; i < 4 ; i++)
16            if(bArray[i] < 0)
17                iArray[i] = 0xff + (int)bArray[i] + 1;
18            else
19                iArray[i] = (int)bArray[i];
20
21        return iArray;
22    }
23 };
```

Lines 4-10 Converts `short` port numbers to `int`.

Lines 12-22 Converts `byte[]` IP addresses to `int[]`.

The converter class is used throughout the examples in the sections below.

Getting Hostnames and Port Numbers

The following code fragments show how it is possible to find out on what hostnames and port numbers a server is listening. First the C++ version:

```
1 // C++
2 OCI::AcceptorSeq_var acceptors = poaManager ->
  get_acceptors();
3
4 for(CORBA::ULong i = 0 ; i < acceptors -> length() ; i++)
5 {
6     OCI::AcceptorInfo_var info = acceptors[i] -> get_info();
7     OCI::IIOP::AcceptorInfo_var iiopInfo =
8         OCI::IIOP::AcceptorInfo::_narrow(info);
9
10    if(!CORBA::is_nil(iiopInfo))
11    {
12        CORBA::StringSeq_var hosts = iiopInfo -> hosts();
13        CORBA::UShort port = iiopInfo -> port();
14
15        cout << "host: " << host[0] << endl;
16        cout << "port: " << port << endl;
17    }
18 }
```

Line 2 The list of registered acceptors is requested from the POA Manager.

Line 4 The `for` loop iterates over all acceptors.

Lines 6-8 The info object for the acceptor is requested and narrowed to an IIOP acceptor info object.

Line 10 The `if` block is only entered in case the info object really belongs to an IIOP plug-in.

Lines 12-16 The hostname and port number are requested from the IIOP acceptor info object and printed on standard output.

The Java version is basically equivalent to the C++ code and looks as follows:

```

1 // Java
2 com.ooc.OCI.Acceptor[] acceptors =
  poaManager.get_acceptors();
3
4 for(int i = 0 ; i < acceptors.length ; i++)
5 {
6     com.ooc.OCI.AcceptorInfo info = acceptors[i].get_info();
7     com.ooc.OCI.IIOP.AcceptorInfo iiopInfo =
8         com.ooc.OCI.IIOP.AcceptorInfoHelper.narrow(info);
9
10    if(iiopInfo != null)
11    {
12        String[] hosts = iiopInfo.hosts();
13        short port = Converter.port(iiopInfo.port());
14
15        System.out.println("host: " + host[0]);
16        System.out.println("port: " + port);
17    }
18 }

```

Lines 2-12 This is equivalent to the C++ version.

Line 13 The converter class is used to get a port number in `int` format.

Lines 15-16 Like in the C++ version, the hostname and port number are printed on standard output.

Determining a Client's IP Address

To determine the IP address of a client within a server method, the following code can be used in a servant class method implementation:

```

1 // C++
2 CORBA::Object_var baseCurrent =
3     orb -> resolve_initial_references("OCICurrent");
4 OCI::Current_var current =
5     OCI::Current::_narrow(baseCurrent);
6 OCI::TransportInfo_var info = current ->
7     get_oci_transport_info();
8 OCI::IIOP::TransportInfo_var iiopInfo =
9     OCI::IIOP::TransportInfo::_narrow(info);
10 if(!CORBA::is_nil(iiopInfo))
11 {
12     OCI::IIOP::InetAddr remoteAddr = iiopInfo ->
13     remote_addr();
14     CORBA::UShort remotePort = iiopInfo -> remote_port();
15     cout << "Call from: "
16         << remoteAddr[0] << '.' << remoteAddr[1] << '.'
17         << remoteAddr[2] << '.' << remoteAddr[3]
18         << ":" << remotePort << endl;
19 }

```

Lines 2-4 The OCI current object is requested and `narrow'd` to the correct `OCI::Current` type.

Lines 6-8 The info object for the transport is requested and `narrow'd` to an IIOP transport info object.

Line 10 The remainder of the example code is only executed if this was really an IIOP transport info object.

Lines 12-18 The address and the port of the client calling this operation are obtained and printed on standard output.

The Java version looks as follows:

```

1 // Java
2 org.omg.CORBA.Object baseCurrent =
3     orb.resolve_initial_references("OCICurrent");
4 com.ooc.OCI.Current current =
5     com.ooc.OCI.CurrentHelper.narrow(baseCurrent);
6
7 com.ooc.OCI.TransportInfo info =
8     current.get_oci_transport_info();
9 com.ooc.OCI.IIOP.TransportInfo iiopInfo =
10    com.ooc.OCI.IIOP.TransportInfoHelper.narrow(baseInfo);
11
12 if(iiopInfo != null)
13 {
14     int[] remoteAddr = Converter.addr(iiopInfo.remote_addr());
15     int remotePort = Converter.port(iiopInfo.remote_port());
16
17     System.out.println("Call from: " +
18         remoteAddr[0] + "." +
19         remoteAddr[1] + "." +
20         remoteAddr[2] + "." +
21         remoteAddr[3] + ":" + remotePort);
22 }

```

Lines 2-11 This code is equivalent to the C++ version.

Lines 13-14 Again, the port number must be converted from `short` to `int`.

Lines 16-20 This is also equivalent to the C++ version.

Determining a Server's IP Address

To determine the server's IP address and port that an object will attempt to connect to, the following code can be used:

```
1 // C++
2 CORBA::Object_var obj = ... // Get an object reference somehow
3
4 OCI::ConnectorInfo_var info = obj -> get_oci_connector_info();
5 OCI::IIOP::ConnectorInfo_var iiopInfo =
6     OCI::IIOP::ConnectorInfo::_narrow(info);
7
8 if(!CORBA::is_nil(iiopInfo))
9 {
10     OCI::IIOP::InetAddr_var remoteAddr = iiopInfo ->
        remoteAddr();
11     CORBA::UShort remotePort = iiopInfo -> remote_port();
12
13     cout << "Will connect to: "
14         << remoteAddr[0] << '.' << remoteAddr[2] << '.'
15         << remoteAddr[2] << '.' << remoteAddr[3]
16         << ":" << remotePort << endl;
17 }
```

Lines 4-6 Get the OCI connector info and narrow to an IIOP connector info

Line 8 The `if` block is only executed if this really was an IIOP connector info.

Lines 10-16 The address and port are obtained and displayed on standard output.

The Java version looks as follows:

```

1 // Java
2 org.omg.CORBA.Object obj = ... // Get an object reference
  somehow
3
4 org.omg.CORBA.portable.ObjectImpl objImpl =
5     (org.omg.CORBA.portable.ObjectImpl) obj;
6 com.ooc.CORBA.Delegate objDelegate =
7     (com.ooc.CORBA.Delegate) objImpl._get_delegate();
8
9 com.ooc.OCI.ConnectorInfo info =
10     objDelegate.get_oci_connector_info();
11 com.ooc.OCI.IIOP.ConnectorInfo iiopInfo =
12     com.ooc.OCI.IIOP.ConnectorInfoHelper.narrow(info);
13
14 if(iiopInfo != null)
15 {
16     int[] remoteAddr = Converter.addr(iiopInfo.remote_addr());
17     int remotePort = Converter.port(iiopInfo.remote_port());
18
19     System.out.println("Will connect to: " +
20                         remoteAddr[0] + "." +
21                         remoteAddr[1] + "." +
22                         remoteAddr[2] + "." +
23                         remoteAddr[3] + ":" + remotePort);
24 }

```

Lines 4-7 We need to retrieve the Orbacus-specific `Delegate` object so that we can get the connector info.

Lines 9-12 Get the OCI connector info and narrow to an IIOP connector info.

Line 14 The `if` block is only entered if this really was an IIOP connector info.

Lines 16-23 The address and port are obtained and displayed on standard output.

The IIOPI OCI Plug-in

The IIOPI plug-in implements the Internet Inter-ORB Protocol as described in [4]. By default, the ORB automatically installs the client and server (that is, Connector Factory and Acceptor Factory) components of the IIOPI plug-in, and IIOPI is the default protocol used by the ORB.

For configuration purposes, the identifier of the IIOPI plug-in is `iiop`.

Client Installation

The client-side IIOPI plug-in is installed as shown below:

```
ooc.oci.client=iiop [--no-keepalive]
```

The following options are supported:

<code>--no-keepalive</code>	Disable the use of TCP keepalives.
-----------------------------	------------------------------------

Server Installation

The server-side IIOPI plug-in is installed as shown below:

```
ooc.oci.server=iiop
```

In this section

This sections covers the following topics:

Endpoint Configuration	page 400
Command-line Options	page 402
Static Linking	page 403

Endpoint Configuration

The configuration options for an IIOp endpoint are shown below:

```
iioP [--backlog N] [--bind ADDR] [--host ADDR[,ADDR,...]]
      [--multi-profile] [--no-keepalive] [--numeric] [--port N]
```

--backlog N	Specifies the maximum length of the listen backlog queue. Note that the operating system may have a smaller limit which will override this value. If not specified, a default value of 50 is used in Java, and 5 in C++.
--bind ADDR	Specifies the hostname or dotted decimal address of the network interface on which to bind the socket. If not specified, the socket will be bound to all available interfaces. This option is useful in situations where a host has several network interfaces, but the server should only listen for connections on a particular interface.
--host ADDR[,ADDR,...]	Specifies a list of one or more hostnames and/or dotted decimal addresses representing the addresses that should be advertised in IORs. Using IIOp 1.0 or 1.1, multiple addresses are represented as multiple tagged profiles. Using IIOp 1.2, multiple addresses can be represented as either multiple tagged profiles, or as a single tagged profile with a tagged component for each additional address. The <code>--multi-profile</code> option determines how multiple addresses are represented in IIOp 1.2. If <code>--host</code> is not specified, the canonical hostname is used.
--multi-profile	If set, multiple addresses in the <code>--host</code> option are represented as multiple tagged profiles in an IOR. By default, multiple addresses are represented as a single tagged profile (using the first address in the <code>--host</code> list as the primary address), with all additional addresses represented as alternate addresses in tagged components. If IIOp 1.0 or 1.1 is in use, multiple addresses are always represented as multiple tagged profiles.

<code>--no-keepalive</code>	Disable the use of TCP keepalives.
<code>--numeric</code>	If set, and if <code>--host</code> is not specified, then the canonical dotted decimal address is advertised in IORs. The default behavior is to use the canonical hostname, if possible.
<code>--port N</code>	Specifies the port number on which to bind the socket. If no port is specified, an unused one will be selected automatically by the operating system. Use this option if you plan to publish an IOR (for example, in a file, a naming service, etc.) and you want that IOR to remain valid across executions of your server. Without this option, your server is likely to use a different port number each time the server is executed. See Chapter 6 for more information.

Command-line Options

The IIOPlug-in supports the following command-line options:

<code>-IIOPl backlog N</code>	Equivalent to the <code>--backlog</code> endpoint option.
<code>-IIOPl bind ADDR</code>	Equivalent to the <code>--bind</code> endpoint option.
<code>-IIOPl host ADDR[,ADDR,...]</code>	Equivalent to the <code>--host</code> endpoint option.
<code>-IIOPl numeric</code>	Equivalent to the <code>--numeric</code> endpoint option.
<code>-IIOPl port N</code>	Equivalent to the <code>--port</code> endpoint option.

See [“Command-line Options and Endpoints” on page 105](#) for more information on the behavior of command-line options.

Static Linking

There are no special requirements for linking the IIOp plug-in statically in C++, since the plug-in is part of the Orbacus core library.

URL Support

The IIOp plug-in supports the standard `iiop` format for `corbaloc` URLs, as described in “corbaloc: URLs” on page 161.

The UDP OCI Plug-in

The UDP plug-in provides unreliable unicast and multicast functionality, suitable for applications which can tolerate the potential for lost messages. Only `oneway` operations are supported.

For configuration purposes, the identifier of the UDP plug-in is `udp`.

In this section

This sections covers the following topics:

Client Installation	page 405
Server Installation	page 406
Static Linking	page 410
URL Support	page 411
Narrowing UDP Object References	page 412

Client Installation

The client-side UDP plug-in is installed as shown below:

```
ooc.oci.client=udp [--buffer-size N] [--packet-delay MSEC]
  [--packet-size N] [--no-loopback] [--ttl N] [--trace N]
```

The following options are supported:

<code>--buffer-size N</code>	Sets the size of the socket's send buffer. Note that this is only a hint to the operating system. To determine the actual size, use the <code>--trace</code> option. The default value is operating-system dependent.
<code>--packet-delay MSEC</code>	Specifies the delay in milliseconds between packets. In some cases, sending packets too quickly can cause more packets to be dropped. The default value is 0.
<code>--packet-size N</code>	Sets the size of a packet in bytes. If necessary, the plug-in splits a single request into multiple packets of the specified size and reassembles them on the server. Note that there are hard operating system limits on the size of a datagram. The default size is 1472, which is the largest portable size.
<code>--no-loopback</code>	Specifies that loopback mode of the socket shall be disabled for multicast communication. This prevents sending multicast packets back to the local socket. For Java this functionality is only available from JDK 1.4.0 on.
<code>--ttl N</code>	Specifies the time-to-live value (0..255) of multicast packets sent. System defaults apply if not specified.
<code>--trace N</code>	Sets the level of diagnostic output. The default value is 0.

Note: The `--no-loopback` option for multicast communication is to be specified on the client side for Unix systems and on the server side for Windows systems.

Server Installation

The server-side UDP plug-in is installed as shown below:

```
ooc.oci.server=udp [--trace N]
```

The following options are supported:

<code>--trace N</code>	Sets the level of diagnostic output. The default value is 0.
------------------------	--

Endpoint Configuration

The configuration options for a UDP endpoint are shown below:

```
udp [--bind ADDR] [--buffer-size N] [--host ADDR[,ADDR,...]]
    [--message-timeout SEC] [--multicast] [--no-loopback]
    [--ttl N] [--numeric] [--port N] [--transport-timeout SEC]
```

<code>--bind ADDR</code>	Specifies the hostname or dotted decimal address of the network interface on which to bind the socket. If not specified, the socket will be bound to all available interfaces. This option is useful in situations where a host has several network interfaces, but the server should only listen for connections on a particular interface.
<code>--buffer-size N</code>	Sets the size of the socket's receive buffer. Note that this is only a hint to the operating system. To determine the actual size, use the <code>--trace</code> option when installing the plug-in. The default value is operating-system dependent.
<code>--host ADDR[,ADDR,...]</code>	Specifies a list of one or more hostnames and/or dotted decimal addresses representing the addresses that should be advertised in IORs. Multiple addresses are represented as multiple tagged profiles. If <code>--host</code> is not specified, the canonical hostname is used. This option must be specified if multicast is used.
<code>--message-timeout SEC</code>	Specifies the expiration time in seconds for incomplete messages. Because the plug-in may fragment a request into multiple packets, it is possible for some packets to be lost. If no more packets have arrived for an incomplete message after the specified timeout, the message is discarded. The default value is 15 seconds.
<code>--multicast</code>	Specifies that multicast should be used. If this option is set, the <code>--host</code> and <code>--port</code> options must also be specified, and the host must be an IP address in the multicast range (224.0.0.0 through 239.255.255.255). By default, multicast is not used.

<code>--no-loopback</code>	Specifies that loopback mode of the socket shall be disabled in multicast mode. This prevents sending multicast packets back to the local socket. For Java this functionality is only available from JDK 1.4.0 on.
<code>--ttl N</code>	Specifies the time-to-live value (0..255) of multicast packets sent. System defaults apply if not specified.
<code>--numeric</code>	If set, and if <code>--host</code> is not specified, then the canonical dotted decimal address is advertised in IORs. The default behavior is to use the canonical hostname, if possible.
<code>--port N</code>	Specifies the port number on which to bind the socket. If no port is specified, an unused one will be selected automatically by the operating system. Use this option if you plan to publish an IOR (for example, in a file, a naming service, etc.) and you want that IOR to remain valid across executions of your server. Without this option, your server is likely to use a different port number each time the server is executed. This option must be specified if multicast is used.
<code>--transport-timeout N</code>	Specifies the time in seconds after which inactive connections are reaped. The default value is 60 seconds.

Note: When using multicast, all servers which belong to the same multicast group must specify the same host address and port. The `--no-loopback` option for multicast communication is to be specified on the client side for Unix systems and on the server side for Windows systems.

Command-line Options

The UDP plug-in supports the following command-line options:

<code>-UDPbind ADDR</code>	Equivalent to the <code>--bind</code> endpoint option.
<code>-UDPHost ADDR[,ADDR,...]</code>	Equivalent to the <code>--host</code> endpoint option.

<code>-UDPmulticast</code>	Equivalent to the <code>--multicast</code> endpoint option.
<code>-UDPnumeric</code>	Equivalent to the <code>--numeric</code> endpoint option.
<code>-UDPport N</code>	Equivalent to the <code>--port</code> endpoint option.

See [“Command-line Options and Endpoints” on page 105](#) for more information on the behavior of command-line options.

Static Linking

When statically a C++ application, an explicit reference must be made to the UDP plug-in in order to include the plug-in's modules. Shown below is the technique used by the sample programs in the `udp/demo` subdirectory. Note that the code below is enclosed in guard macros that are only activated when statically linking. These macros are appropriate for both Unix and Windows. First, extra include files are necessary:

```
#if !defined(HAVE_SHARED) && !defined(OB_DLL)
#include <OB/OCI_init.h>
#include <OB/OCI_UDP_init.h>
#endif
```

Next, the plug-in must be registered prior to calling `ORB_init()`:

```
#if !defined(HAVE_SHARED) && !defined(OB_DLL)
//
// When linking statically, we need to explicitly register
// the plug-in prior to ORB initialization
//
OCI::register_plugin("udp", OCI_init_udp);
#endif
```

URL Support

The UDP plug-in supports `corbaloc` URLs with the following protocol syntax:

```
corbaloc:udp:host:port/object-key
```

The components of the URL are as follows:

- `udp` - This selects the UDP plug-in.
- `host` - The hostname or IP address of the server.
- `port` - The port on which the server is listening.
- `object-key` - A stringified object key.

Narrowing UDP Object References

When an application calls `narrow()`, it may result in the ORB making a twoway call to the `_is_a()` operation to determine whether `narrow()` should succeed. However, twoway operations cannot be invoked on UDP object references, therefore the application must take extra precautions.

It is only safe to use `narrow()` when:

- the object reference has a non-empty repository ID¹, and
- the repository ID matches the type being narrowed.

In all other cases, the ORB will attempt to invoke `_is_a()`.

Therefore, if an application cannot be sure that `narrow()` will succeed without invoking `_is_a()`, it should use the standard operation `unchecked_narrow()` instead. This operation assumes that the application is operating correctly and allows the narrow to succeed without using `_is_a()`.

1. Object references created from `corbaloc` URLs always have empty repository IDs.

The Bi-directional OCI Plug-in

Note: This Bidir implementation is deprecated with the addition of the CORBA 3 compliant version of BiDir GIOP. New users requiring BiDir functionality should use the new BiDir GIOP interface as described in [Chapter 16](#).

Overview

The Orbacus Bi-directional plug-in offers a solution for distributed systems where security restrictions interfere with a client's ability to receive callbacks.

This capability is especially useful in two common situations:

- Firewalls prevent the server from establishing a separate connection back to the client
- Browser restrictions prevent an applet from accepting connections

Note: This plug-in does not implement the Bi-directional IOP standard defined by CORBA 2.3. This plug-in uses a proprietary protocol that is not interoperable with other ORBs.

In this section

This sections covers the following topics:


How Does it Work?	page 415
Peers	page 416
Client Installation	page 417
Server Installation	page 418
Endpoint Configuration	page 419
Command-line Options	page 420
Configuration Properties	page 421
Static Linking	page 422

How Does it Work?

The Bi-directional plug-in uses a layered design that theoretically enables any connection-oriented OCI plug-in to support bi-directional functionality. Initially however, only bi-directional IIOp is supported.

In [Figure 16](#), a server is shown that is capable of receiving both bi-directional IIOp connections and regular IIOp connections.

Figure 16: *Connection Requirements*



Any callback requests from the Server to Client A will travel down the existing connection already established by the client. On the other hand, any callback requests from the Server to Client B require a new IIOp connection to be established from the server to the client.

Peers

The Bi-directional plug-in requires each peer in a bi-directional connection to have a unique identifier, called the peer ID. Currently, this identifier is just a simple ISO-LATIN1 string. In IIOp terms, a unique endpoint is derived from the hostname/port combination. However, since the Bi-directional OCI plug-in has no knowledge of the underlying protocol, a separate identification scheme is currently required, and must be provided by the application. It is therefore the application's responsibility to ensure that each server and client has a unique peer ID.

In IIOp, object references can be made persistent (valid across process restarts) by ensuring that the process is restarted on the same host and port, and that the object keys in the object references will continue to be valid. The same is true of peer IDs. If you want a bidirectional IIOp object reference to remain valid across process restarts, you must use the same peer ID, host, port and object key. Conversely, if an object reference is transient, then the peer ID can vary along with the host, port and object key.

Client Installation

The client-side bi-directional plug-in is installed as shown below:

```
ooc.oci.client=ID [options], bidir --protocol ID
```

The following options are supported:

<code>--protocol ID</code>	Specifies the identifier of the underlying plug-in. This parameter is required.
----------------------------	---

Because the bi-directional plug-in is layered on another plug-in, the underlying plug-in must be installed first. For example, to install bi-directional IIOP, the IIOP plug-in is installed first, and then the bi-directional plug-in is installed:

```
ooc.oci.client=iiop, bidir --protocol iiop
```

Note that a bi-directional application generally needs to install both the client- and server-side plug-ins.

Server Installation

The server-side bi-directional plug-in is installed as shown below:

```
ooc.oci.server=ID [options], bidir --protocol ID
```

The following options are supported:

<code>--protocol ID</code>	Specifies the identifier of the underlying plug-in. This parameter is required.
----------------------------	---

Because the bi-directional plug-in is layered on another plug-in, the underlying plug-in must be installed first. For example, to install bi-directional IIOP, the IIOP plug-in is installed first, and then the bi-directional plug-in is installed:

```
ooc.oci.server=iiop, bidir --protocol iiop
```

Note that a bi-directional application generally needs to install both the client- and server-side plug-ins.

Endpoint Configuration

There are two distinct types of bi-directional endpoints: one which creates a real endpoint using the underlying plug-in, and one which only listens for callbacks on existing, outgoing bi-directional connections. The latter type will be referred to as a callback endpoint.

A server will typically create the first type of endpoint; a security-restricted client will only create the second type, since listening on a real port is often forbidden (or pointless, if a firewall prevents incoming connections).

The implication of creating a callback endpoint is that a server wishing to call back to a client will only be able to do so if there is an existing bi-directional connection from the client to the server. If not, the server will receive a `TRANSIENT` exception.

The configuration options for a bi-directional endpoint are shown below. Note that the plug-in identifier for endpoint configuration purposes is formed by combining `bidir_` with the identifier of the underlying plug-in (for example, `bidir_iiop`).

```
bidir_ID [--callback] [options]
```

The only option supported by the bi-directional plug-in is `--callback`, which creates a callback endpoint. If this option is specified, it must be the only option.

If `--callback` is not the first and only option, all additional options are passed to the underlying plug-in for processing. For example, a server would typically use a configuration such as:

```
ooc.orb.oa.endpoint=bidir_iiop --port 7000
```

This creates a bi-directional IIOp endpoint on the static port 7000.

On the other hand, a bi-directional client would use the following configuration:

```
ooc.orb.oa.endpoint=bidir_iiop --callback
```

This creates a callback endpoint which can only receive requests when an existing, outgoing bi-directional IIOp connection has been established from this client to the server that wishes to make a callback.

Command-line Options

No command-line options are supported.

Configuration Properties

The bi-directional plug-in supports a single configuration property:

<code>ooc.bidir.peer</code>	Specifies the peer ID. If not specified, a unique peer ID is used.
-----------------------------	--

Static Linking

When statically a C++ application, an explicit reference must be made to the bi-directional plug-in (as well as to the underlying plug-in) in order to include the plug-in's modules. Shown below is the technique used by the sample programs in the `bidir/demo` subdirectory. Note that the code below is enclosed in guard macros that are only activated when statically linking. These macros are appropriate for both Unix and Windows. First, extra include files are necessary:

```
#if !defined(HAVE_SHARED) && !defined(OB_DLL)
#include <OB/OCI_init.h>
#include <OB/OCI_BiDir_init.h>
#endif
```

Next, the plug-in must be registered prior to calling `ORB_init()`:

```
#if !defined(HAVE_SHARED) && !defined(OB_DLL)
//
// When linking statically, we need to explicitly register
// the plug-in prior to ORB initialization
//
OCI::register_plugin("bidir", OCI_init_bidir);
#endif
```

URL Support

The bi-directional plug-in supports `corbaloc` URLs with the following protocol syntax:

```
corbaloc:bidir_ID:peer/object-key
corbaloc:bidir_ID:peer:[options]/object-key
```

The first form indicates a callback endpoint, whereas the second form indicates an endpoint using an underlying plug-in.

The components of the URL are as follows:

- `bidir_ID` - This selects the bi-directional plug-in using the underlying plug-in identified by `ID`.
- `peer` - The peer ID.
- `options` - Options specific to the underlying plug-in.
- `object-key` - A stringified object key.

For example:

```
corbaloc:bidir_iiop:Client/Foo
corbaloc:bidir_iiop:Server:thehost:9999/Foo
```

The first example is a URL for a bi-directional IIOp callback endpoint. The second example is a URL for a bi-directional IIOp endpoint on host `thehost` and port `9999`.

Exceptions and Error Messages

In this chapter

This chapter contains the following sections:

CORBA System Exceptions	page 426
Non-Compliant Application Asserts	page 445

CORBA System Exceptions

The CORBA specification defines the standard system exceptions shown in the following table.

UNKNOWN	Unknown exception type
BAD_PARAM	An invalid parameter was passed
NO_MEMORY	Failure to allocate dynamic memory
IMP_LIMIT	Implementation limit was violated
COMM_FAILURE	Communication failure
INV_OBJREF	Invalid object reference
NO_PERMISSION	The attempted operation was not permitted
INTERNAL	Internal error in ORB
MARSHAL	Error marshalling a parameter or result
INITIALIZE	Failure when initializing ORB
NO_IMPLEMENT	Operation implementation unavailable
BAD_TYPECODE	Bad typecode
BAD_OPERATION	Invalid operation
NO_RESOURCES	Insufficient resources for a request
NO_RESPONSE	Response to a request is not yet available
PERSIST_STORE	Persistent storage failure
BAD_INV_ORDER	Routine invocation out of order
TRANSIENT	Transient failure, request can be reissued
FREE_MEM	Cannot free memory
INV_IDENT	Invalid identifier syntax
INV_FLAG	Invalid flag was specified

INTF_REPOS	Error accessing interface repository
BAD_CONTEXT	Error processing context object
OBJ_ADAPTER	Failure detected by object adapter
DATA_CONVERSION	Error in data conversion
OBJECT_NOT_EXIST	Non-existent object, references should be discarded
TRANSACTION_REQUIRED	Active transaction context required
TRANSACTION_ROLLEDBACK	Transaction has rolled back or is marked to be rolled back
INVALID_TRANSACTION	Invalid transaction context
INV_POLICY	Invalid Policy
CODESET_INCOMPATIBLE	Incompatible client and server native code sets
REBIND	Thrown on a OBJECT_FORWARD or LOCATION_FORWARD status, depending on the RebindPolicy
TIMEOUT	Time-to-live period was exceeded
TRANSACTION_UNAVAILABLE	Transaction service context could not be processed
TRANSACTION_MODE	Mismatch between TransactionPolicy and current transaction mode
BAD_QOS	Object cannot support the required QOS

In the following subsections the minor exception codes are presented. Minor codes that are Orbacus-specific are presented as *MinorCodeName*^{*}, that is, are tagged with the superscript '*'.

In this section

This section describes the following minor exception codes:

INITIALIZE Minor Exception Code	page 429
UNKNOWN Minor Exception Code	page 430

BAD_PARAM Minor Exception Code	page 431
NO_MEMORY Minor Exception Code	page 433
IMP_LIMIT Minor Exception Code	page 434
COMM_FAILURE Minor Exception Code	page 435
MARSHAL Minor Exception Code	page 436
NO_IMPLEMENT Minor Exception Code	page 438
NO_RESOURCES Minor Exception Code	page 439
BAD_INV_ORDER Minor Exception Code	page 440
TRANSIENT Minor Exception Code	page 441
INTF_REPOS Minor Exception Code	page 442
OBJECT_NOT_EXIST Minor Exception Code	page 443
INV_POLICY Minor Exception Code	page 444

INITIALIZE Minor Exception Code

MinorORBDestroyed	ORB already destroyed
-------------------	-----------------------

UNKNOWN Minor Exception Code

MinorUnknownUserException	Unknown user exception
---------------------------	------------------------

BAD_PARAM Minor Exception Code

MinorValueFactoryError	Failure to register, unregister or lookup value factory
MinorRepositoryIdExists	Repository ID already exists in Interface Repository
MinorNameExists	Name already used in Interface Repository
MinorInvalidContainer	Target is not a valid container
MinorNameClashInInheritedContext	Name clash in inherited context
MinorBadAbstractInterfaceType	Incorrect type for abstract interface
MinorBadSchemeName	Bad scheme name
MinorBadAddress	Bad address
MinorBadSchemeSpecificPart	Bad scheme specific part
MinorOther	Other
MinorInvalidAbstractInterfaceInheritance	Invalid abstract interface inheritance
MinorInvalidValueInheritance	Invalid valuetype inheritance
MinorInvalidServiceContextId	Invalid service context ID
MinorObjectIsNull	Object parameter to <code>object_to_ior()</code> is null
MinorInvalidComponentId	Invalid component ID
MinorInvalidProfileId	Invalid profile ID
MinorDuplicatePolicyType	Duplicate policy types
MinorDuplicateDeclarator*	Duplicate declarator
MinorInvalidValueModifier*	Invalid valuetype modifier
MinorDuplicateValueInit*	Duplicate valuetype initializer
MinorAbstractValueInit*	Abstract valuetype cannot have initializer

MinorDuplicateBaseType [*]	Base type appears more than once
MinorSingleThreadedOnly [*]	ORB does not support multiple threads
MinorNameRedefinitionInImmediateScope [*]	Invalid name redefinition in an immediate scope
MinorInvalidValueBoxType [*]	Invalid type for valuebox
MinorInvalidLocalInterfaceInheritance [*]	Invalid local interface inheritance
MinorConstantTypeMismatch [*]	Constant type doesn't match definition

NO_MEMORY Minor Exception Code

MinorAllocationFailure*	Memory allocation failure
-------------------------	---------------------------

IMP_LIMIT Minor Exception Code

MinorNoUsableProfile	No usable profile in IOR
MinorMessageSizeLimit [*]	Maximum message size exceeded
MinorThreadLimit [*]	Can't create new thread

COMM_FAILURE Minor Exception Code

MinorRecv [*]	recv() failed
MinorSend [*]	send() failed
MinorRecvZero [*]	recv() returned zero
MinorSendZero [*]	send() returned zero
MinorSocket [*]	socket() failed
MinorSetsockopt [*]	setsockopt() failed
MinorGetsockopt [*]	getsockopt() failed
MinorBind [*]	bind() failed
MinorListen [*]	listen() failed
MinorConnect [*]	connect() failed
MinorAccept [*]	accept() failed
MinorSelect [*]	select() failed
MinorGethostname [*]	gethostname() failed
MinorGethostbyname [*]	gethostbyname() failed
MinorWSAStartup [*]	WSAStartup() failed
MinorWSACleanup [*]	WSACleanup() failed
MinorNoGIOP [*]	Not a GIOP message
MinorUnknownMessage [*]	Unknown GIOP message
MinorWrongMessage [*]	Wrong GIOP message
MinorMessageError [*]	Got a message error message
MinorFragment [*]	Invalid fragment message
MinorUnknownReqId [*]	Unknown request ID
MinorVersion [*]	Incompatible GIOP version
MinorPipe [*]	Creation of pipe failed
MinorSetSoTimeout [*]	setSoTimeout() failed

MARSHAL Minor Exception Code

MinorNoValueFactory	Unable to locate value factory
MinorDSIResultBeforeContext	DSI result cannot be set before context
MinorDSIInvalidParameterList	DSI argument list does not describe all parameters
MinorLocalObject	Attempt to marshal local object
MinorWcharSentByClient	wchar data sent by client on GIOP 1.0 connection
MinorWcharSentByServer	wchar data returned by server on GIOP 1.0 connection
MinorReadOverflow [*]	Input stream buffer overflow
MinorReadBooleanOverflow [*]	Overflow while reading boolean
MinorReadCharOverflow [*]	Overflow while reading char
MinorReadWCharOverflow [*]	Overflow while reading wchar
MinorReadOctetOverflow [*]	Overflow while reading octet
MinorReadShortOverflow [*]	Overflow while reading short
MinorReadUShortOverflow [*]	Overflow while reading ushort
MinorReadLongOverflow [*]	Overflow while reading long
MinorReadULongOverflow [*]	Overflow while reading ulong
MinorReadLongLongOverflow [*]	Overflow while reading longlong
MinorReadULongLongOverflow [*]	Overflow while reading ulonglong
MinorReadFloatOverflow [*]	Overflow while reading float
MinorReadDoubleOverflow [*]	Overflow while reading double
MinorReadLongDoubleOverflow [*]	Overflow while reading longdouble
MinorReadStringOverflow [*]	Overflow while reading string
MinorReadStringZeroLength [*]	Encountered zero-length string
MinorReadStringNullChar [*]	Encountered null char in string

MinorReadStringNoTerminator [*]	Terminating null char missing in string
MinorReadWStringOverflow [*]	Overflow while reading wstring
MinorReadWStringZeroLength [*]	Encountered zero-length wstring
MinorReadWStringNullWChar [*]	Encountered null char in wstring
MinorReadWStringNoTerminator [*]	Terminating null char missing in wstring
MinorReadFixedOverflow [*]	Overflow while reading fixed
MinorReadFixedInvalid [*]	Invalid encoding for fixed value
MinorReadBooleanArrayOverflow [*]	Overflow while reading boolean array
MinorReadCharArrayOverflow [*]	Overflow while reading char array
MinorReadWCharArrayOverflow [*]	Overflow while reading wchar array
MinorReadOctetArrayOverflow [*]	Overflow while reading octet array
MinorReadShortArrayOverflow [*]	Overflow while reading short array
MinorReadUShortArrayOverflow [*]	Overflow while reading ushort array
MinorReadLongArrayOverflow [*]	Overflow while reading long array
MinorReadULongArrayOverflow [*]	Overflow while reading ulong array
MinorReadLongLongArrayOverflow [*]	Overflow while reading longlong array
MinorReadULongLongArrayOverflow [*]	Overflow while reading ulonglong array
MinorReadFloatArrayOverflow [*]	Overflow while reading float array
MinorReadDoubleArrayOverflow [*]	Overflow while reading double array
MinorReadLongDoubleArrayOverflow [*]	Overflow while reading longdouble array
MinorReadInvTypeCodeIndirection [*]	Invalid type code indirection
MinorWriteObjectLocal [*]	Attempt to marshal a locality-constrained object
MinorLongDoubleNotSupported [*]	Long double is not supported

NO_IMPLEMENT Minor Exception Code

<code>MinorMissingLocalValueImplementation</code>	Missing local value implementation
<code>MinorIncompatibleValueImplementationVersion</code>	Incompatible value implementation version
<code>MinorNotSupportedByLocalObject</code>	Operation not supported by local object
<code>MinorDIINotSupportedByLocalObject</code>	DII operation not supported by local object

NO_RESOURCES Minor Exception Code

MinorInvalidBinding	Portable Interceptor operation not supported in binding
---------------------	---

BAD_INV_ORDER Minor Exception Code

MinorDependencyPreventsDestruction	Dependency exists in Interface Repository prevents destruction of object
MinorIndestructibleObject	Attempt to destroy indestructible object in Interface Repository
MinorDestroyWouldBlock	Operation would deadlock
MinorShutdownCalled	ORB has shutdown
MinorDuplicateSend	Request has already been sent
MinorServantManagerAlreadySet	Servant manager already set
MinorInvalidUseOfDSIArguments	Invalid use of DSI arguments
MinorInvalidUseOfDSIContext	Invalid use of DSI context
MinorRequestAlreadySent	DII request has already been sent
MinorRequestNotSent	DII request has not been sent yet
MinorResponseAlreadyReceived	DII response has already been received
MinorSynchronousRequest	Operation not supported on synchronous DII request
MinorInvalidPICall	Invalid Portable Interceptor call
MinorServiceContextExists	A service context already exists with the given ID
MinorPolicyFactoryExists	A factory already exists for the given PolicyType
MinorNoCreatePOA	Cannot create POA while undergoing destruction
MinorBadConcModel [*]	Invalid concurrency model
MinorORBRunning [*]	ORB::run() already called

TRANSIENT Minor Exception Code

MinorRequestDiscarded	Request has been discarded
MinorNoUsableProfileInIOR	No usable profile in IOR
MinorRequestCancelled	Request has been cancelled
MinorPOADestroyed	POA has been destroyed
MinorConnectFailed*	Request has been cancelled
MinorCloseConnection*	Got a 'close connection' message
MinorActiveConnectionManagement*	Active connection management closed connection
MinorForcedShutdown*	Forced connection shutdown because of timeout
MinorLocationForwardHopCountExceeded*	Forced connection shutdown because of timeout

INTF_REPOS Minor Exception Code

MinorNoIntfRepos [*]	Interface Repository is not available
MinorLookupAmbiguous [*]	Search name for <code>lookup()</code> is ambiguous
MinorIllegalRecursion [*]	Illegal Recursion
MinorNoEntry [*]	IFR is not populated with a required definition.

OBJECT_NOT_EXIST Minor Exception Code

MinorUnregisteredValue	Attempt to pass unactivated (unregistered) value as an object reference
MinorCannotDispatch	Unable to dispatch - servant or POA not found

INV_POLICY Minor Exception Code

MinorCannotReconcilePolicy	Cannot reconcile IOR policy with effective policy override
MinorInvalidPolicyType	Invalid PolicyType
MinorNoPolicyFactory	No PolicyFactory for the PolicyType has been registered

Non-Compliant Application Asserts

If the Orbacus library was compiled without the preprocessor definition `-DNDEBUG` defined, Orbacus tries to detect common programming mistakes that lead to non-compliant CORBA applications. If such a mistake is found an error messages like this will appear:

```
Non-compliant application error detected:
Application used wrong memory allocation function
```

After detecting such an error, the Orbacus library dumps a core (Unix only) and prints the file and line number where the error was detected. You can use the core dump in order to track down the problem with a debugger.

The following error messages can appear:

Application requested a feature that has not yet been implemented This is not an application error. This error message appears if an application attempts to use a feature that has not yet been implemented in Orbacus. In this case the only thing that can be done is to wait for the next Orbacus version that has this particular feature implemented.

Application used a deprecated feature that is not implemented anymore This is not an application error. This error message appears if an application attempts to use a feature that is no longer implemented in Orbacus. In this case the only thing that can be done is to avoid using this particular feature.

Application used wrong memory allocation function If this message appears, an incorrect memory allocation function has been used. A common mistake that leads to this error is to use `malloc`, `strdup` and `free` (or the `new` and `delete` operator) instead of `CORBA::string_alloc` and `CORBA::string_dup` and `CORBA::string_free` for string memory management.

Message	Description
Memory that was already deallocated was deallocated again	This message indicates multiple memory deallocations. For example, if <code>CORBA::string_free</code> is called twice on the same string, this message will be displayed.
Object was deleted without an object reference count of zero	This message appears if an object was deleted by calling <code>delete</code> on its object reference. Never use the <code>delete</code> operator for that; use <code>CORBA::release</code> instead.

Message	Description
Object was already deleted (object reference count was already zero)	This message appears if the number of <code>release</code> operations on an object reference is greater than the number of <code>_duplicate</code> operations.
Sequence length was greater than maximum sequence length	This message indicates that the application tried to set the length of a bounded sequence to a value greater than its maximum length.
Index for sequence operator[]() or remove() function was out of range	This message appears if the argument to the sequence member functions <code>operator[]</code> or <code>remove</code> exceeds the sequence length.
Buffer size not equal to sequence bound	This message indicates that the application attempted to call <code>allocbuf</code> on a bounded sequence with an argument not equal to the sequence bound.
Null pointer was used to initialize T_var type	This message indicates an attempt to initialize a <code>_var</code> type with a null pointer.
operator->() was used on null pointer or nil object reference	This message indicates an attempt to use <code>operator-></code> on an uninitialized <code>_var</code> type.
Application tried to dereference a null pointer	Some CORBA <code>_var</code> types have built-in conversion operators to a C++ reference type. That is, some <code>_var</code> types for type <code>T</code> have a conversion operator to <code>T&</code> . This message appears if an application uses this conversion operator on an uninitialized <code>_var</code> type.
Null pointer was passed as string parameter or return value	According to the IDL-to-C++ mapping specification, no null pointers may be passed as string parameters or return values. This message appears if an application tries to do so.
Null value passed as parameter	This message indicates that an application attempted to pass a null value across an IDL interface.

Message	Description
Self assignment caused a dangling pointer	<p>This message appears if the content of a <code>_var</code> type is assigned to itself. For example, the following code will lead to this error message:</p> <pre>// Somehow get a pointer to a variable struct AVariableStruct_var var = ... AVariableStruct* ptr = var; var = ptr;</pre> <p>This will result in a dangling pointer, because <code>var</code> will free its own content on assignment.</p>
Replacement of Any content by its own value caused a dangling pointer	<p>This message appears if there is an attempt to replace the content of an <code>Any</code> by its own value. For example:</p> <pre>char* s = CORBA::string_dup("Hello, world!"); CORBA::Any any; any <<= s; any <<= s;</pre> <p>Inserting <code>s</code> into <code>any</code> twice will result in a dangling pointer, because <code>any</code> will free its own value (which is <code>s</code>) on assignment.</p>
Invalid union discriminator type used	<p>This message appears if the discriminator type argument to <code>CORBA::ORB::create_union_tc</code> denotes a type invalid for union discriminators. Valid types have a <code>CORBA::TKind</code> that is one of <code>CORBA::tk_short</code>, <code>CORBA::tk_ushort</code>, <code>CORBA::tk_long</code>, <code>CORBA::tk_ulong</code>, <code>CORBA::tk_char</code>, <code>CORBA::tk_boolean</code> or <code>CORBA::tk_enum</code>.</p>
Union discriminator mismatch	<p>This message either indicates an attempt to set a union discriminator to an invalid value with the <code>_d</code> modifier function or the use of a wrong accessor function: an accessor function that does not correspond to the type of the union's actual value.</p>
Uninitialized union used	<p>If this message appears, a union was used that was created with the default constructor and that was not set to any legal value.</p>

Message	Description
CORBA::Any::operator<<=(Exception*) cannot be used with --no-type-codes	This message indicates that CORBA::Any::operator<<=(Exception*) was invoked for an exception for which no TypeCode is available. That is, the IDL defining the exception was compiled with the --no-typecodes option.
An operation on an unembedded recursive TypeCode was invoked	If this message appears, an operation was invoked on a recursive TypeCode that has not yet been embedded.
An already embedded TypeCode was reused	This message indicates that an application attempted to embed a recursive TypeCode that was already embedded.
LongDouble type is not supported on this platform	This message appears when an application uses the CORBA::LongDouble type on a platform which does not support this type.

Boot Manager Reference

This appendix describes the interfaces for the Orbacus Boot Manager.

In this appendix

This appendix contains the following sections:

Interface OB::BootManager	page 450
Interface OB::BootLocator	page 452

Interface OB::BootManager

```
local interface BootManager
Interface to manage bootstrapping of objects.
```

Exceptions

NotFound

```
exception NotFound
{
};
```

This exception indicates that a binding has not been found.

AlreadyExists

```
exception AlreadyExists
{
};
```

This exception indicates that a binding already exists.

Operations

add_binding

```
void add_binding(in PortableServer::ObjectId oid,
                in Object obj)
    raises(AlreadyExists);
```

Add a new binding to the internal table.

Parameters:

oid – The object id to bind.

obj – The object reference.

Raises:

AlreadyExists – Thrown if binding already exists.

remove_binding

```
void remove_binding(in PortableServer::ObjectId oid)
    raises(NotFound);
```

Remove a binding from the internal table.

Parameters:

oid – The object id to remove.

Raises:

NotFound – Thrown if no binding found.

set_locator

```
void set_locator(in BootLocator locator);
```

Set the BootLocator. The BootLocator is called when a binding for an object id does not exist in the internal table.

Parameters:

`locator` – The BootLocator reference.

See Also:

[“Interface OB::BootLocator”](#)

Interface OB::BootLocator

```
local interface BootLocator
```

Interface used by BootManager to assist in locating objects.

See Also:

[“Interface OB::BootManager”](#)

Operations

locate

```
void locate(in PortableServer::ObjectId oid,  
            out Object obj,  
            out boolean add)  
            raises(BootManager::NotFound);
```

Locate the object corresponding to the given object id.

Parameters:

oid – The object id.

obj – The object reference to associate with the id.

add – Whether the binding should be added to the internal table.

Raises:

NotFound – Raised if no binding found.

Orbacus Policy Reference

This appendix describes the Orbacus Policy interfaces.

In this appendix

This appendix contains the following sections:

Module OB	page 454
Module OBPortableServer	page 465
BiDirPolicy	page 467

Module OB

Constants

CONNECTION_REUSE_POLICY_ID

```
const CORBA::PolicyType CONNECTION_REUSE_POLICY_ID = 1330577411;
```

This policy type identifies the connection reuse policy.

CONNECT_TIMEOUT_POLICY_ID

```
const CORBA::PolicyType CONNECT_TIMEOUT_POLICY_ID = 1330577416;
```

This policy type identifies the connect timeout policy.

INTERCEPTOR_POLICY_ID

```
const CORBA::PolicyType INTERCEPTOR_POLICY_ID = 1330577415;
```

This policy type identifies the interceptor policy.

LOCATE_REQUEST_POLICY_ID

```
const CORBA::PolicyType LOCATE_REQUEST_POLICY_ID = 1330577418;
```

This policy type identifies the locate request policy.

LOCATION_TRANSPARENCY_POLICY_ID

```
const CORBA::PolicyType LOCATION_TRANSPARENCY_POLICY_ID =  
1330577414;
```

This policy type identifies the location transparency policy.

LOCATION_TRANSPARENCY_RELAXED

```
const short LOCATION_TRANSPARENCY_RELAXED = 1;
```

The `LOCATION_TRANSPARENCY_RELAXED` `LocationTransparencyPolicy` value.

LOCATION_TRANSPARENCY_STRICT

```
const short LOCATION_TRANSPARENCY_STRICT = 0;
```

The `LOCATION_TRANSPARENCY_STRICT` `LocationTransparencyPolicy` value.

PROTOCOL_POLICY_ID

```
const CORBA::PolicyType PROTOCOL_POLICY_ID = 1330577410;
```

This policy type identifies the protocol policy.

REQUEST_TIMEOUT_POLICY_ID

```
const CORBA::PolicyType REQUEST_TIMEOUT_POLICY_ID = 1330577417;
```

This policy type identifies the request timeout policy.

RETRY_ALWAYS

```
const short RETRY_ALWAYS = 2;
```

The `RETRY_ALWAYS` RetryPolicy value.

RETRY_NEVER

```
const short RETRY_NEVER = 0;
```

The `RETRY_NEVER` RetryPolicy value.

RETRY_POLICY_ID

```
const CORBA::PolicyType RETRY_POLICY_ID = 1330577412;
```

This policy type identifies the retry policy.

RETRY_STRICT

```
const short RETRY_STRICT = 1;
```

The `RETRY_STRICT` RetryPolicy value.

TIMEOUT_POLICY_ID

```
const CORBA::PolicyType TIMEOUT_POLICY_ID = 1330577413;
```

This policy type identifies the timeout policy.

Structs**RetryAttributes**

```
struct RetryAttributes
{
    short mode;
    unsigned long interval;
    unsigned long max;
    boolean remote;
};
```

The retry information

Interface OB::ConnectTimeoutPolicy

```
local interface ConnectTimeoutPolicy
inherits from CORBA::Policy
```

The connect timeout policy. This policy can be used to specify a maximum time limit for connection establishment.

See Also:

[“Interface OB::TimeoutPolicy”](#)

Attributes

value

```
readonly attribute unsigned long value;
```

If an object has a `ConnectTimeoutPolicy` set and a connection cannot be established after `value` milliseconds, a `CORBA:NO_RESPONSE` exception is raised. The default value is `-1`, which means no timeout.

Interface OB::ConnectionReusePolicy

```
local interface ConnectionReusePolicy
inherits from CORBA::Policy
```

The connection reuse policy. This policy determines whether connections may be reused or are private to specific objects.

Attributes

value

```
readonly attribute boolean value;
```

If an object has a `ConnectionReusePolicy` set with `value` set to `FALSE`, then other object references will not be permitted to use connections made on behalf of this object. If set to `TRUE`, then connections are shared. The default value is `TRUE`.

Interface OB::InterceptorPolicy

```
local interface InterceptorPolicy
inherits from CORBA::Policy
```

The interceptor policy. This policy can be used to control whether the client-side interceptors are called.

Attributes

value

```
readonly attribute boolean value;
```

If an object reference has an `InterceptorPolicy` set and `value` is `FALSE` then any installed client-side interceptors are not called. Otherwise, interceptors are called for each method invocation. The default value is `TRUE`.

Interface OB::LocateRequestPolicy

```
local interface LocateRequestPolicy
inherits from CORBA::Policy
```

The locate request policy. This policy can be used to specify whether the ORB sends locate request messages.

Attributes

value

```
readonly attribute boolean value;
```

If an object has a `LocateRequestPolicy` set to `false` then the ORB will not send locate request messages for the object.

Interface OB::LocationTransparencyPolicy

```
local interface LocationTransparencyPolicy
inherits from CORBA::Policy
```

The location transparency policy. This policy is used to control how strict the ORB is in enforcing location transparency. This is useful for performance reasons.

Attributes

value

```
readonly attribute short value;
```

LOCATION_TRANSPARENCY_STRICT ensures strict location transparency is followed. LOCATION_TRANSPARENCY_RELAXED relaxes the location transparency guarantees for performance reasons. Specifically for collocated method invocations, the dispatch concurrency model will be ignored, and policy overrides are not removed. The default value is LOCATION_TRANSPARENCY_RELAXED.

Interface OB::ProtocolPolicy

```
local interface ProtocolPolicy
inherits from CORBA::Policy
```

The protocol policy. This policy specifies the order in which profiles should be tried.

Attributes

value

```
readonly attribute OCI::PluginIdSeq value;
```

If a `ProtocolPolicy` is set, then the value specifies the list of plugins that may be used. The profiles of an IOR will be used in the order specified by this policy. If no profile in an IOR matches any of the plugins specified by this policy, a `CORBA::TRANSIENT` exception will be raised. By default, the ORB chooses the protocol to be used.

Operations

contains

```
boolean contains(in OCI::PluginId id);
```

Determines if this policy includes the given plugin id.

Interface OB::RequestTimeoutPolicy

```
local interface RequestTimeoutPolicy
inherits from CORBA::Policy
```

The request timeout policy. This policy can be used to specify a maximum time limit for requests.

See Also:

[“Interface OB::TimeoutPolicy”](#)

Attributes

value

```
readonly attribute unsigned long value;
```

If an object has a `RequestTimeoutPolicy` set and no response to a request is available after `value` milliseconds, a `CORBA::NO_RESPONSE` exception is raised. The default value is `-1`, which means no timeout.

Interface OB::RetryPolicy

```
local interface RetryPolicy
inherits from CORBA::Policy
```

The retry policy. This policy is used to specify retry behavior after communication failures (that is, `CORBA::TRANSIENT` and `CORBA::COMM_FAILURE` exceptions).

Attributes

retry_interval

```
readonly attribute unsigned long retry_interval;
```

retry_max

```
readonly attribute unsigned long retry_max;
```

retry_mode

```
readonly attribute short retry_mode;
```

For `retry_mode` `RETRY_NEVER` indicates that requests should never be retried, and the exception is re-thrown to the application. `RETRY_STRICT` will retry once if the exception completion status is `COMPLETED_NO`, in order to guarantee at-most-once semantics. `RETRY_ALWAYS` will retry once, regardless of the exception completion status. The default value is `RETRY_STRICT`. `retry_interval` is the time in milliseconds between retries. The default is 0. `retry_max` is the maximum number of retries. The default is 1.

`retry_remote` determines whether or not to retry on exceptions received over-the-wire. The default is `false`: only retry on locally generated exceptions. **Note:** Many TCP/IP stacks do not provide a reliable indication of communication failure when sending smaller requests, therefore the failure may not be detected until the ORB attempts to read the reply. In this case, the ORB must assume that the remote end has received the request, in order to guarantee at-most-once semantics for the request. The implication is that when using the default setting of `RETRY_STRICT`, most communication failures will not cause a retry. This behavior can be relaxed using `RETRY_ALWAYS`.

retry_remote

```
readonly attribute boolean retry_remote;
```

Interface `OB::TimeoutPolicy`

```
local interface TimeoutPolicy
inherits from CORBA::Policy
```

The timeout policy. This policy can be used to specify the default timeout for connection establishment and requests. If an object also has `ConnectionTimeoutPolicy` or `RequestTimeoutPolicy` set, those values have precedence.

See Also:

[“Interface `OB::ConnectTimeoutPolicy`”](#)

[“Interface `OB::RequestTimeoutPolicy`”](#)

Attributes

value

```
readonly attribute unsigned long value;
```

If an object has a `TimeoutPolicy` set and a connection cannot be established or no response to a request is available after `value` milliseconds, a `CORBA::NO_RESPONSE` exception is raised. The default value is `-1`, which means no timeout.

Module OBPortableServer

Constants

INTERCEPTOR_CALL_POLICY_ID

```
const CORBA::PolicyType INTERCEPTOR_CALL_POLICY_ID = 1330577667;
```

This policy type identifies the interceptor call policy.

Interface `OBPortableServer::InterceptorCallPolicy`

```
local interface InterceptorCallPolicy
inherits from CORBA::Policy
```

The interceptor call policy. This policy controls whether the server-side interceptors are called for a particular POA.

Attributes

value

```
readonly attribute boolean value;
```

The `InterceptorCallPolicy` value. If a POA has an `InterceptorCallPolicy` set and `value` is `FALSE` then any installed server-side interceptors are not called for requests on this POA. Otherwise, interceptors are called for each request. The default value is `TRUE`.

BiDirPolicy

Constants

BIDIRECTIONAL_POLICY_TYPE

```
const CORBA::PolicyType BIDIRECTIONAL_POLICY_TYPE = 37;
```

This policy type identifies the BiDirectional GIOP (CORBA 3 compliant) protocol policy.

NORMAL

```
const BidirectionalPolicyValue NORMAL = 0;
```

This value indicates normal (disabled) BiDir GIOP functionality.

BOTH

```
const BidirectionalPolicyValue BOTH = 1;
```

This value indicates enabled BiDir GIOP functionality.

Typedefs

```
typedef unsigned short BidirectionalPolicyValue;
```


Reactor Reference

This appendix describes the Orbacus Reactor interfaces.

In this appendix

This appendix contains the following section:

Module OB	page 470
---------------------------	--------------------------

Module OB

Aliases

Handle

```
typedef long Handle;
```

An event handler's handle.

Mask

```
typedef long Mask;
```

An event handler's mask. The mask determines which events the event handler is interested in.

TypeMask

```
typedef long TypeMask;
```

An event handler's type mask. The type mask determines which category the event handler belongs to. A value of zero means no specific category.

Constants

EventRead

```
const Mask EventRead = 1;
```

The mask for read events.

EventWrite

```
const Mask EventWrite = 2;
```

The mask for write events.

TypeClient

```
const TypeMask TypeClient = 1;
```

The type mask for client event handlers.

TypeServer

```
const TypeMask TypeServer = 2;
```

The type mask for server event handlers.

Native Types

EventHandler

```
native EventHandler;
```

An event handler is a native type.

Interface OB::Reactor

local interface Reactor
A generic Reactor interface.

Operations

register_handler

```
void register_handler(in EventHandler handler,  
                    in Mask handler_mask,  
                    in TypeMask type_mask,  
                    in Handle h);
```

Register an event handler with the Reactor, or change the registration of an already registered event handler.

Parameters:

`handler` – The event handler to register.

`mask` – The type of events the event handler is interested in.

`type_mask` – The category the event handler belongs to.

`h` – The event handler's handle.

unregister_handler

```
void unregister_handler(in EventHandler handler);
```

Remove an event handler from the Reactor.

Parameters:

`handler` – The event handler to remove.

dispatch

```
boolean dispatch(in TypeMask type_mask);
```

Dispatch events.

Parameters:

`type_mask` – If not zero, this operation will return once all registered event handlers that match the type mask have unregistered.

Returns:

`TRUE` if all event handlers that match the type mask have unregistered, or
`FALSE` if event dispatching has been interrupted.

interrupt_dispatch

```
void interrupt_dispatch();
```

Interrupt event dispatching. After calling this operation, `interrupt()` will return with `FALSE`.

dispatch_one_event

```
boolean dispatch_one_event(in long timeout);
```

Dispatch at least one event.

Parameters:

`timeout` – The timeout in milliseconds. A negative value means no timeout: the operation will not return before at least one event has been dispatched. A zero timeout means that the operation will return immediately if there is no event to dispatch.

Returns:

`TRUE` if at least one event has been dispatched, or `FALSE` otherwise.

event_ready

```
boolean event_ready();
```

Check whether an event is available.

Returns:

`TRUE` if an event is ready, or `FALSE` otherwise.

Logger Reference

This appendix describes the Orbacus Logger interfaces.

In this appendix

This appendix contains the following sections:

Interface OB::Logger	page 474
Interface OB::WLogger	page 475

Interface **OB::Logger**

local interface Logger
The Orbacus message logger interface.

Operations

info

void info(in string msg);
Log an informational message.
Parameters:
msg – The message.

error

void error(in string msg);
Log an error message.
Parameters:
msg – The error message.

warning

void warning(in string msg);
Log a warning message.
Parameters:
msg – The warning message.

trace

void trace(in string category,
 in string msg);
Log a trace message.
Parameters:
category – The trace category.
msg – The trace message.

Interface OB::WLogger

```
local interface WLogger : Logger
```

The Orbacus message logger interface with support for wide strings.

Operations

winfo

```
void winfo(in wstring msg);
```

Log an informational message.

Parameters:

`msg` – The message.

werror

```
void werror(in wstring msg);
```

Log an error message.

Parameters:

`msg` – The error message.

wwarning

```
void wwarning(in wstring msg);
```

Log a warning message.

Parameters:

`msg` – The warning message.

wtrace

```
void wtrace(in wstring category,  
            in wstring msg);
```

Log a trace message.

Parameters:

`category` – The trace category.

`msg` – The trace message.

Open Communications Interface Reference

This appendix describes the interfaces for the Open Communication Interface.

In this appendix

This appendix contains the following sections:

Module OCI	page 478
Module OCI::IIOP	page 513

Module OCI

Aliases

BufferSeq

```
typedef sequence<Buffer> BufferSeq;
```

Alias for a sequence of buffers.

IOR

```
typedef IOP::IOR IOR;
```

Alias for an IOR.

ProfileId

```
typedef IOP::ProfileId ProfileId;
```

Alias for a profile id.

ProfileIdSeq

```
typedef sequence<ProfileId> ProfileIdSeq;
```

Alias for a sequence of profile ids.

PluginId

```
typedef string PluginId;
```

Alias for a plugin id.

PluginIdSeq

```
typedef sequence<PluginId> PluginIdSeq;
```

Alias for a sequence of plugin ids.

ObjectKey

```
typedef CORBA::OctetSeq ObjectKey;
```

Alias for an object key, which is a sequence of octets.

TaggedComponentSeq

```
typedef IOP::TaggedComponentSeq TaggedComponentSeq;
```

Alias for a sequence of tagged components.

Handle

```
typedef long Handle;
```

Alias for a system-specific handle type.

ProfileInfoSeq

```
typedef sequence<ProfileInfo> ProfileInfoSeq;
```

Alias for a sequence of basic information about profiles.

ParamSeq

```
typedef sequence<string> ParamSeq;
```

Alias for a sequence of parameters.

CloseCBSeq

```
typedef sequence<CloseCB> CloseCBSeq;
```

Alias for a sequence of close callback objects.

ConnectorSeq

```
typedef sequence<Connector> ConnectorSeq;
```

Alias for a sequence of Connectors.

ConnectCBSeq

```
typedef sequence<ConnectCB> ConnectCBSeq;
```

Alias for a sequence of connect callback objects.

ConFactorySeq

```
typedef sequence<ConFactory> ConFactorySeq;
```

Alias for a sequence of Connector factories.

AcceptorSeq

```
typedef sequence<Acceptor> AcceptorSeq;
```

Alias for a sequence of Acceptors.

AcceptCBSeq

```
typedef sequence<AcceptCB> AcceptCBSeq;
```

Alias for a sequence of accept callback objects.

AccFactorySeq

```
typedef sequence<AccFactory> AccFactorySeq;
```

Alias for a sequence of AccFactory objects.

Constants**Version**

```
const string Version = "1.0";
```

The OCI version. If an interface or implementation changes in an incompatible way, this version will be changed.

Enums**SendReceiveMode**

```
enum SendReceiveMode
{
    SendOnly,
    ReceiveOnly,
    SendReceive
};
```

Indicates the send/receive capabilities of an OCI component.

Structs**ProfileInfo**

```
struct ProfileInfo
{
    ObjectKey key;
    octet major;
    octet minor;
    ProfileId id;
    unsigned long index;
    TaggedComponentSeq components;
};
```

Basic information about an IOR profile. Profiles for specific protocols contain additional data. (For example, an IIOP profile also contains a hostname and a port number.)

Members:

`key` – The object key.

`major` – The major version number of the ORB's protocol. (For example, the major GIOP version, if the underlying ORB uses GIOP.)

`minor` – The minor version number of the ORB's protocol. (For example, the minor GIOP version, if the underlying ORB uses GIOP.)

`id` – The id of the profile that contains this information.

`index` – The position index of this profile in an IOR.

`components` – A sequence of tagged components.

Exceptions**FactoryAlreadyExists**

```
exception FactoryAlreadyExists
{
    PluginId id;
};
```

A factory with the given plugin id already exists.

Members:

`id` – The plugin id.

NoSuchFactory

```
exception NoSuchFactory
{
    PluginId id;
};
```

No factory with the given plugin id could be found.

Members:

`id` – The plugin id.

InvalidParam

```
exception InvalidParam
{
    string reason;
};
```

A parameter is invalid.

Members:

`reason` – A description of the error.

Interface OCI::Buffer

Synopsis

```
local interface Buffer
```

An interface for a buffer. A buffer can be viewed as an object holding an array of octets and a position counter, which determines how many octets have already been sent or received. The IDL interface definition for Buffer is incomplete and must be extended by the specific language mappings. For example, the C++ mapping defines the following additional functions:

- `Octet* data()`: Returns a C++ pointer to the first element of the array of octets, which represents the buffer's contents.
- `Octet* rest()`: Similar to `data()`, this operation returns a C++ pointer, but to the n-th element of the array of octets with n being the value of the position counter.

Attributes

length

```
readonly attribute unsigned long length;
```

The buffer length.

pos

```
attribute unsigned long pos;
```

The position counter. Note that the buffer's length and the position counter don't depend on each other. There are no restrictions on the values permitted for the counter. This implies that it's even legal to set the counter to values beyond the buffer's length.

Operations

advance

```
void advance(in unsigned long delta);
```

Increment the position counter.

Parameters:

`delta` – The value to add to the position counter.

rest_length

```
unsigned long rest_length();
```

Returns the rest length of the buffer. The rest length is the length minus the position counter's value. If the value of the position counter exceeds the buffer's length, the return value is undefined.

Returns:

The rest length.

is_full

```
boolean is_full();
```

Checks if the buffer is full. The buffer is considered full if its length is equal to the position counter's value.

Returns:

`TRUE` if the buffer is full, `FALSE` otherwise.

Interface OCI::Plugin

Synopsis

```
local interface Plugin
```

The interface for a Plugin object, which is used to initialize an OCI plug-in.

Attributes

id

```
readonly attribute PluginId id;
```

The plugin id.

tag

```
readonly attribute ProfileId tag;
```

The profile id tag.

Operations

init_client

```
void init_client(in ParamSeq params);
```

Initialize the client-side of the plug-in.

Parameters:

params – Plug-in specific parameters.

init_server

```
void init_server(in ParamSeq params);
```

Initialize the server-side of the plug-in.

Parameters:

params – Plug-in specific parameters.

Interface OCI::Transport

Synopsis

```
local interface Transport
```

The interface for a Transport object, which provides operations for sending and receiving octet streams. In addition, it is possible to register callbacks with the Transport object, which are invoked whenever data can be sent or received without blocking.

See Also:

[“Interface OCI::Connector”](#)

[“Interface OCI::Acceptor”](#)

Attributes

id

```
readonly attribute PluginId id;
```

The plugin id.

tag

```
readonly attribute ProfileId tag;
```

The profile id tag.

mode

```
readonly attribute SendReceiveMode mode;
```

The send/receive capabilities of this Transport.

handle

```
readonly attribute Handle handle;
```

The handle for this Transport. The handle may *only* be used to determine whether the Transport object is ready to send or to receive data, for example, with `select()` on Unix-based operating systems. All other uses (for example, calls to `read()`, `write()`, `close()`) are strictly non-compliant. A handle value of -1 indicates that the protocol plug-in does not support selectable Transports.

Operations

close

```
void close();
```

Closes the Transport. After calling `close`, no operations on this Transport object and its associated `TransportInfo` object may be called. To ensure that no messages get lost when `close` is called, `shutdown` should be called first. Then dummy data should be read from the Transport, using one of the `receive` operations, until either an exception is raised, or until connection closure is detected. After that its safe to call `close`; that is, no messages can get lost.

Raises:

`COMM_FAILURE` – In case of an error.

shutdown

```
void shutdown();
```

Shutdown the Transport. Upon a successful shutdown, threads blocking in the `receive` operations will return or throw an exception. After calling `shutdown`, no operations on associated `TransportInfo` object may be called. To fully close the Transport, `close` must be called.

Raises:

`COMM_FAILURE` – In case of an error.

receive

```
void receive(in Buffer buf,
            in boolean block);
```

Receives a buffer's contents.

Parameters:

`buf` – The buffer to fill.

`block` – If set to `TRUE`, the operation blocks until the buffer is full. If set to `FALSE`, the operation fills as much of the buffer as possible without blocking.

Raises:

`COMM_FAILURE` – In case of an error.

receive_detect

```
boolean receive_detect(in Buffer buf,
                      in boolean block);
```

Similar to `receive`, but it signals a connection loss by returning `FALSE` instead of raising `COMM_FAILURE`.

Parameters:

`buf` – The buffer to fill.

`block` – If set to `TRUE`, the operation blocks until the buffer is full. If set to `FALSE`, the operation fills as much of the buffer as possible without blocking.

Returns:

`FALSE` if a connection loss is detected, `TRUE` otherwise.

Raises:

`COMM_FAILURE` – In case of an error.

receive_timeout

```
void receive_timeout(in Buffer buf,
                    in unsigned long timeout);
```

Similar to `receive`, but it is possible to specify a timeout. On return the caller can test whether there was a timeout by checking if the buffer has been filled completely.

Parameters:

`buf` – The buffer to fill.

`timeout` – The timeout value in milliseconds. A zero timeout is equivalent to calling `receive(buf, FALSE)`.

Raises:

`COMM_FAILURE` – In case of an error.

receive_timeout_detect

```
boolean receive_timeout_detect(in Buffer buf,
                               in unsigned long timeout);
```

Similar to `receive_timeout`, but it signals a connection loss by returning `FALSE` instead of raising `COMM_FAILURE`.

Parameters:

`buf` – The buffer to fill.

`timeout` – The timeout value in milliseconds. A zero timeout is equivalent to calling `receive(buf, FALSE)`.

Returns:

`FALSE` if a connection loss is detected, `TRUE` otherwise.

Raises:

`COMM_FAILURE` – In case of an error.

send

```
void send(in Buffer buf,
          in boolean block);
```

Sends a buffer's contents.

Parameters:

`buf` – The buffer to send.

`block` – If set to `TRUE`, the operation blocks until the buffer has completely been sent. If set to `FALSE`, the operation sends as much of the buffer's data as possible without blocking.

Raises:

`COMM_FAILURE` – In case of an error.

send_detect

```
boolean send_detect(in Buffer buf,
                   in boolean block);
```

Similar to `send`, but it signals a connection loss by returning `FALSE` instead of raising `COMM_FAILURE`.

Parameters:

`buf` – The buffer to fill.

`block` – If set to `TRUE`, the operation blocks until the entire buffer has been sent. If set to `FALSE`, the operation sends as much of the buffer's data as possible without blocking.

Returns:

`FALSE` if a connection loss is detected, `TRUE` otherwise.

Raises:

`COMM_FAILURE` – In case of an error.

send_timeout

```
void send_timeout(in Buffer buf,
                 in unsigned long timeout);
```

Similar to `send`, but it is possible to specify a timeout. On return, the caller can test whether there was a timeout by checking if the buffer has been sent completely.

Parameters:

`buf` – The buffer to send.

`timeout` – The timeout value in milliseconds. A zero timeout is equivalent to calling `send(buf, FALSE)`.

Raises:

`COMM_FAILURE` – In case of an error.

send_timeout_detect

```
boolean send_timeout_detect(in Buffer buf,  
                           in unsigned long timeout);
```

Similar to `send_timeout`, but it signals a connection loss by returning `FALSE` instead of raising `COMM_FAILURE`.

Parameters:

`buf` – The buffer to fill.

`timeout` – The timeout value in milliseconds. A zero timeout is equivalent to calling `send(buf, FALSE)`.

Returns:

`FALSE` if a connection loss is detected, `TRUE` otherwise.

Raises:

`COMM_FAILURE` – In case of an error.

get_info

```
TransportInfo get_info();
```

Returns the information object associated with the Transport.

Returns:

The Transport information object.

Interface OCI::TransportInfo

Synopsis

```
local interface TransportInfo
```

Information on an OCI Transport object. Objects of this type must be narrowed to a Transport information object for a concrete protocol implementation, for example to `OCI::IIOP::TransportInfo` in case the plug-in implements IIOP.

See Also:

[“Interface OCI::Transport”](#)

Attributes

id

```
readonly attribute PluginId id;
```

The plugin id.

tag

```
readonly attribute ProfileId tag;
```

The profile id tag.

connector_info

```
readonly attribute ConnectorInfo connector_info;
```

The ConnectorInfo object for the Connector that created the Transport object that this TransportInfo object belongs to. If the Transport for this TransportInfo was not created by a Connector, this attribute is set to the nil object reference.

acceptor_info

```
readonly attribute AcceptorInfo acceptor_info;
```

The AcceptorInfo object for the Acceptor that created the Transport object that this TransportInfo object belongs to. If the Transport for this TransportInfo was not created by an Acceptor, this attribute is set to the nil object reference.

Operations

describe

```
string describe();
```

Returns a human readable description of the transport.

Returns:

The description.

add_close_cb

```
void add_close_cb(in CloseCB cb);
```

Add a callback that is called before a connection is closed. If the callback has already been registered, this method has no effect.

Parameters:

cb – The callback to add.

remove_close_cb

```
void remove_close_cb(in CloseCB cb);
```

Remove a close callback. If the callback was not registered, this method has no effect.

Parameters:

cb – The callback to remove.

Interface OCI::CloseCB

Synopsis

```
local interface CloseCB
```

An interface for a close callback object.

See Also:

[“Interface OCI::TransportInfo”](#)

Operations

close_cb

```
void close_cb(in TransportInfo transport_info);
```

Called before a connection is closed.

Parameters:

`transport_info` – The TransportInfo for the new closeion.

Interface OCI::Connector

Synopsis

```
local interface Connector
```

An interface for Connector objects. A Connector is used by CORBA clients to initiate a connection to a server. It also provides operations for the management of IOR profiles.

See Also:

[“Interface OCI::ConFactory”](#)

[“Interface OCI::Transport”](#)

Attributes

id

```
readonly attribute PluginId id;
```

The plugin id.

tag

```
readonly attribute ProfileId tag;
```

The profile id tag.

Operations

connect

```
Transport connect();
```

Used by CORBA clients to establish a connection to a CORBA server. It returns a Transport object, which can be used for sending and receiving octet streams to and from the server.

Returns:

The new Transport object.

Raises:

`TRANSIENT` – If the server cannot be contacted.

`COMM_FAILURE` – In case of other errors.

connect_timeout

```
Transport connect_timeout(in unsigned long timeout);
```

Similar to `connect`, but it is possible to specify a timeout. On return the caller can test whether there was a timeout by checking whether a nil object reference was returned.

Parameters:

`timeout` – The timeout value in milliseconds.

Returns:

The new Transport object.

Raises:

`TRANSIENT` – If the server cannot be contacted.

`COMM_FAILURE` – In case of other errors.

get_usable_profiles

```
ProfileInfoSeq get_usable_profiles(in IOR ref,
                                   in CORBA::PolicyList policies);
```

From the given IOR and list of policies, get basic information about all profiles for which this Connector can be used.

Parameters:

`ref` – The IOR from which the profiles are taken.

`policies` – The policies that must be satisfied.

Returns:

The sequence of basic information about profiles. If this sequence is empty, there is no profile in the IOR that matches this Connector and the list of policies.

equal

```
boolean equal(in Connector con);
```

Find out whether this Connector is equal to another Connector. Two Connectors are considered equal if they are interchangeable.

Parameters:

`con` – The connector to compare with.

Returns:

`TRUE` if the Connectors are equal, `FALSE` otherwise.

get_info

```
ConnectorInfo get_info();
```

Returns the information object associated with the Connector.

Returns:

The Connector information object.

Interface OCI::ConnectorInfo

Synopsis

```
local interface ConnectorInfo
```

Information on a OCI Connector object. Objects of this type must be narrowed to a Connector information object for a concrete protocol implementation, for example to `OCI::IIOP::ConnectorInfo` in case the plug-in implements IIOP.

See Also:

[“Interface OCI::Connector”](#)

Attributes

id

```
readonly attribute PluginId id;
```

The plugin id.

tag

```
readonly attribute ProfileId tag;
```

The profile id tag.

Operations

describe

```
string describe();
```

Returns a human readable description of the transport.

Returns:

The description.

add_connect_cb

```
void add_connect_cb(in ConnectCB cb);
```

Add a callback that is called whenever a new connection is established. If the callback has already been registered, this method has no effect.

Parameters:

cb – The callback to add.

remove_connect_cb

```
void remove_connect_cb(in ConnectCB cb);
```

Remove a connect callback. If the callback was not registered, this method has no effect.

Parameters:

cb – The callback to remove.

Interface OCI::ConnectCB

Synopsis

```
local interface ConnectCB
```

An interface for a connect callback object.

See Also:

[“Interface OCI::ConnectorInfo”](#)

Operations

connect_cb

```
void connect_cb(in TransportInfo transport_info);
```

Called after a new connection has been established. If the application wishes to reject the connection `CORBA::NO_PERMISSION` may be raised.

Parameters:

`transport_info` – The `TransportInfo` for the new connection.

Interface OCI::ConFactory

Synopsis

```
local interface ConFactory
A factory for Connector objects.
```

See Also:

[“Interface OCI::Connector”](#)

[“Interface OCI::ConFactoryRegistry”](#)

Attributes

id

```
readonly attribute PluginId id;
```

The plugin id.

tag

```
readonly attribute ProfileId tag;
```

The profile id tag.

Operations

describe_profile

```
string describe_profile(in IOP::TaggedProfile prof);
```

Returns a description of the given tagged profile.

Parameters:

prof – The tagged profile.

Returns:

The profile description.

create_connectors

```
ConnectorSeq create_connectors(in IOR ref,
                               in CORBA::PolicyList policies);
```

Returns a sequence of Connectors for a given IOR and a list of policies. The sequence includes one or more Connectors for each IOR profile that matches this Connector factory and satisfies the list of policies.

Parameters:

ref – The IOR for which Connectors are returned.

policies – The policies that must be satisfied.

Returns:

The sequence of Connectors.

equivalent

```
boolean equivalent(in IOR ior1,  
                  in IOR ior2);
```

Checks whether two IORs are equivalent, taking only profiles into account matching this Connector factory.

Parameters:

`ior1` – The first IOR to check for equivalence.

`ior2` – The second IOR to check for equivalence.

Returns:

`TRUE` if the IORs are equivalent, `FALSE` otherwise.

hash

```
unsigned long hash(in IOR ref,  
                  in unsigned long maximum);
```

Calculates a hash value for an IOR.

Parameters:

`ref` – The IOR to calculate a hash value for.

`maximum` – The maximum value of the hash value.

Returns:

The hash value.

get_info

```
ConFactoryInfo get_info();
```

Returns the information object associated with the Connector factory.

Returns:

The Connector factory information object.

Interface OCI::ConFactoryInfo

Synopsis

```
local interface ConFactoryInfo
```

Information on an OCI ConFactory object.

See Also:

[“Interface OCI::ConFactory”](#)

Attributes

id

```
readonly attribute PluginId id;
```

The plugin id.

tag

```
readonly attribute ProfileId tag;
```

The profile id tag.

Operations

describe

```
string describe();
```

Returns a human readable description of the transport.

Returns:

The description.

add_connect_cb

```
void add_connect_cb(in ConnectCB cb);
```

Add a callback that is called whenever a new connection is established. If the callback has already been registered, this method has no effect.

Parameters:

cb – The callback to add.

remove_connect_cb

```
void remove_connect_cb(in ConnectCB cb);
```

Remove a connect callback. If the callback was not registered, this method has no effect.

Parameters:

cb – The callback to remove.

Interface OCI::ConFactoryRegistry

Synopsis

```
local interface ConFactoryRegistry
```

A registry for Connector factories.

See Also:

[“Interface OCI::Connector”](#)

[“Interface OCI::ConFactory”](#)

Operations

add_factory

```
void add_factory(in ConFactory factory)
    raises(FactoryAlreadyExists);
```

Adds a Connector factory to the registry.

Parameters:

factory – The Connector factory to add.

Raises:

FactoryAlreadyExists – If a factory already exists with the same plugin id as the given factory.

get_factory

```
ConFactory get_factory(in PluginId id)
    raises(NoSuchFactory);
```

Returns the factory with the given plugin id.

Parameters:

id – The plugin id.

Returns:

The Connector factory.

Raises:

NoSuchFactory – If no factory was found with a matching plugin id.

get_factories

```
ConFactorySeq get_factories();
```

Returns all registered factories.

Returns:

The Connector factories.

Interface OCI::Acceptor

Synopsis

```
local interface Acceptor
```

An interface for an Acceptor object, which is used by CORBA servers to accept client connection requests. It also provides operations for the management of IOR profiles.

See Also:

[“Interface OCI::AccFactoryRegistry”](#)

[“Interface OCI::AccFactory”](#)

[“Interface OCI::Transport”](#)

Attributes

id

```
readonly attribute PluginId id;
```

The plugin id.

tag

```
readonly attribute ProfileId tag;
```

The profile id tag.

handle

```
readonly attribute Handle handle;
```

The handle for this Acceptor. Like with the handle for Transports, the handle may *only* be used with operations like `select()`. A handle value of -1 indicates that the protocol plug-in does not support selectable Transports.

Operations

close

```
void close();
```

Closes the Acceptor. `accept` or `listen` may not be called after `close` has been called.

Raises:

`COMM_FAILURE` – In case of an error.

shutdown

```
void shutdown();
```

Shutdown the Acceptor. After shutdown, the socket will not listen to further connection requests.

Raises:

`COMM_FAILURE` – In case of an error.

listen

```
void listen();
```

Sets the acceptor up to listen for incoming connections. Until this method is called on the acceptor, new connection requests should result in a connection request failure.

Raises:

`COMM_FAILURE` – In case of an error.

accept

```
Transport accept(in boolean block);
```

Used by CORBA servers to accept client connection requests. It returns a Transport object, which can be used for sending and receiving octet streams to and from the client.

Parameters:

`block` – If set to `TRUE`, the operation blocks until a new connection has been accepted. If set to `FALSE`, the operation returns a nil object reference if there is no new connection ready to be accepted.

Returns:

The new Transport object.

Raises:

`COMM_FAILURE` – In case of an error.

connect_self

```
Transport connect_self();
```

Connect to this acceptor. This operation can be used to unblock threads that are blocking in `accept`.

Returns:

The new Transport object.

Raises:

`TRANSIENT` – If the server cannot be contacted.

`COMM_FAILURE` – In case of other errors.

add_profiles

```
void add_profiles(in ProfileInfo profile_info,  
                 inout IOR ref);
```

Add new profiles that match this Acceptor to an IOR.

Parameters:

`profile_info` – The basic profile information to use for the new profiles.

`ref` – The IOR.

get_local_profiles

```
ProfileInfoSeq get_local_profiles(in IOR ref);
```

From the given IOR, get basic information about all profiles for which are local to this Acceptor.

Parameters:

`ref` – The IOR from which the profiles are taken.

Returns:

The sequence of basic information about profiles. If this sequence is empty, there is no profile in the IOR that is local to the Acceptor.

get_info

```
AcceptorInfo get_info();
```

Returns the information object associated with the Acceptor.

Returns:

The Acceptor information object.

Interface OCI::AcceptorInfo

Synopsis

```
local interface AcceptorInfo
```

Information on an OCI Acceptor object. Objects of this type must be narrowed to an Acceptor information object for a concrete protocol implementation, for example to `OCI::IIOP::AcceptorInfo` in case the plug-in implements IIOP.

See Also:

[“Interface OCI::Acceptor”](#)

Attributes

id

```
readonly attribute PluginId id;
```

The plugin id.

tag

```
readonly attribute ProfileId tag;
```

The profile id tag.

Operations

describe

```
string describe();
```

Returns a human readable description of the transport.

Returns:

The description.

add_accept_cb

```
void add_accept_cb(in AcceptCB cb);
```

Add a callback that is called whenever a new connection is accepted. If the callback has already been registered, this method has no effect.

Parameters:

`cb` – The callback to add.

remove_accept_cb

```
void remove_accept_cb(in AcceptCB cb);
```

Remove an accept callback. If the callback was not registered, this method has no effect.

Parameters:

cb – The callback to remove.

Interface OCI::AcceptCB

Synopsis

```
local interface AcceptCB
```

An interface for an accept callback object.

See Also:

[“Interface OCI::AcceptorInfo”](#)

Operations

accept_cb

```
void accept_cb(in TransportInfo transport_info);
```

Called after a new connection has been accepted. If the application wishes to reject the connection `CORBA::NO_PERMISSION` may be raised.

Parameters:

`transport_info` – The TransportInfo for the new connection.

Interface OCI::AccFactory

Synopsis

```
local interface AccFactory
```

An interface for an AccFactory object, which is used by CORBA servers to create Acceptors.

See Also:

[“Interface OCI::Acceptor”](#)

[“Interface OCI::AccFactoryRegistry”](#)

Attributes

id

```
readonly attribute PluginId id;
```

The plugin id.

tag

```
readonly attribute ProfileId tag;
```

The profile id tag.

Operations

create_acceptor

```
Acceptor create_acceptor(in ParamSeq params)
    raises(InvalidParam);
```

Create an Acceptor using the given configuration parameters. Refer to the plug-in documentation for a description of the configuration parameters supported for a particular protocol.

Parameters:

params – The configuration parameters.

Returns:

The new Acceptor.

Raises:

InvalidParam – If any of the parameters are invalid.

change_key

```
void change_key(inout IOP::IOR ior,
    in ObjectKey key);
```

Change the object-key in the IOR profile for this given protocol.

Parameters:

`ior` – The IOR

`key` – The new object key

get_info

`AccFactoryInfo get_info();`

Returns the information object associated with the Acceptor factory.

Returns:

The Acceptor

Interface OCI::AccFactoryInfo

Synopsis

```
local interface AccFactoryInfo
Information on an OCI AccFactory object.
See Also:
“Interface OCI::AccFactory”
```

Attributes

```
id
readonly attribute PluginId id;
The plugin id.

tag
readonly attribute ProfileId tag;
The profile id tag.
```

Operations

```
describe
string describe();
Returns a human readable description of the transport.
Returns:
The description.
```

Interface OCI::AccFactoryRegistry

Synopsis

```
local interface AccFactoryRegistry
```

A registry for Acceptor factories.

See Also:

[“Interface OCI::Acceptor”](#)

[“Interface OCI::AccFactory”](#)

Operations

add_factory

```
void add_factory(in AccFactory factory)
    raises (FactoryAlreadyExists);
```

Adds an Acceptor factory to the registry.

Parameters:

factory – The Acceptor factory to add.

Raises:

FactoryAlreadyExists – If a factory already exists with the same plugin id as the given factory.

get_factory

```
AccFactory get_factory(in PluginId id)
    raises (NoSuchFactory);
```

Returns the factory with the given plugin id.

Parameters:

id – The plugin id.

Returns:

The Acceptor factory.

Raises:

NoSuchFactory – If no factory was found with a matching plugin id.

get_factories

```
AccFactorySeq get_factories();
```

Returns all registered factories.

Returns:

The Acceptor factories.

Interface OCI::Current

Synopsis

```
local interface Current
inherits from CORBA::Current
```

Interface to access Transport and Acceptor information objects related to the current request.

Operations

get_oci_transport_info

```
TransportInfo get_oci_transport_info();
```

This method returns the Transport information object for the Transport used to invoke the current request.

get_oci_acceptor_info

```
AcceptorInfo get_oci_acceptor_info();
```

This method returns the Acceptor information object for the Acceptor which created the Transport used to invoke the current request.

Module OCI::IIOP

This module contains interfaces to support the IIOP OCI plug-in.

Aliases

InetAddr

```
typedef string InetAddr
```

Alias for an IP address. This alias will be used for address information from the various information classes. It can be an IPv4 or IPv6 address string.

Constants

PLUGIN_ID

```
const PluginId PLUGIN_ID = "iiop";
```

The identifier for the Orbacus IIOP plug-in.

Interface OCI::IIOP::TransportInfo

Synopsis

```
local interface TransportInfo
inherits from OCI::TransportInfo
Information on an IIOP OCI Transport object.
See Also:
“Interface OCI::Transport”
“Interface OCI::TransportInfo”
```

Attributes

addr

```
readonly attribute InetAddr addr;
The local IP address.
```

port

```
readonly attribute unsigned short port;
The local port.
```

remote_addr

```
readonly attribute InetAddr remote_addr;
The remote IP address.
```

remote_port

```
readonly attribute unsigned short remote_port;
The remote port.
```

Interface OCI::IIOP::ConnectorInfo

Synopsis

```
local interface ConnectorInfo
inherits from OCI::ConnectorInfo
```

Information on an IIOP OCI Connector object.

See Also:

[“Interface OCI::Connector”](#)

[“Interface OCI::ConnectorInfo”](#)

Attributes

remote_addr

```
readonly attribute InetAddr remote_addr;
```

The remote IP address to which this connector connects.

remote_port

```
readonly attribute unsigned short remote_port;
```

The remote port to which this connector connects.

Interface OCI::IIOP::ConFactoryInfo

Synopsis

```
local interface ConFactoryInfo  
inherits from OCI::ConFactoryInfo
```

Information on an IIOP OCI Connector Factory object.

See Also:

[“Interface OCI::ConFactory”](#)

[“Interface OCI::ConFactoryInfo”](#)

Interface OCI::IIOP::AcceptorInfo

Synopsis

```
local interface AcceptorInfo
inherits from OCI::AcceptorInfo
Information on an IIOP OCI Acceptor object.
See Also:
"Interface OCI::Acceptor"
"Interface OCI::AcceptorInfo"
```

Attributes

hosts

```
readonly attribute CORBA::StringSeq hosts;
Hostnames used for creation of IIOP object references.
```

addr

```
readonly attribute InetAddr addr;
The local IP address on which this acceptor accepts.
```

port

```
readonly attribute unsigned short port;
The local port on which this acceptor accepts.
```

Interface OCI::IIOP::AccFactoryInfo

Synopsis

```
local interface AccFactoryInfo  
inherits from OCI::AccFactoryInfo
```

Information on an IIOP OCI Acceptor Factory object.

Orbacus Balancer Reference

This appendix describes the interfaces for the Orbacus Balancer.

In this appendix

This appendix contains the following sections:

Module LoadBalancing	page 520
Module LoadBalancing::Util	page 531

Module LoadBalancing

The definitions in this module provide the interface of the Orbacus Balancer.

Aliases

GroupId

```
typedef string GroupId;
```

A load balanced group ID.

GroupIdSeq

```
typedef sequence<GroupId> GroupIdSeq;
```

A sequence of load balanced group IDs.

MemberId

```
typedef string MemberId;
```

A member ID.

MemberIdSeq

```
typedef sequence<MemberId> MemberIdSeq;
```

A sequence of member IDs.

ObjectId

```
typedef PortableInterceptor::ObjectId ObjectId;
```

An object ID.

PropertyName

```
typedef string PropertyName;
```

A load balancing strategy configuration property name.

PropertyValue

```
typedef any PropertyValue;
```

A load balancing strategy configuration property value.

PropertySeq

```
typedef sequence<Property> PropertySeq;
```

A sequence of load balancing strategy configuration properties.

PropertyErrorSeq

```
typedef sequence<PropertyError> PropertyErrorSeq;
```

A sequence of load balancing strategy configuration property errors.

MemberDataSeq

```
typedef sequence<MemberData> MemberDataSeq;
```

A sequence of member data.

TolerancePropertyValue

```
typedef unsigned long TolerancePropertyValue;
```

The tolerance load balancing strategy property value. The default value is 0.

LoadPerClientPropertyType

```
typedef unsigned long LoadPerClientPropertyType;
```

The load-per-client load balancing strategy property value. The default value is 0.

RejectPropertyValue

```
typedef unsigned long RejectPropertyValue;
```

The reject-load load balancing strategy property value. The default value is 0, meaning no rejections.

DampeningMultiplierPropertyValue

```
typedef float DampeningMultiplierPropertyValue;
```

The dampening-multiplier load balancing strategy property value. The default value is 0, which disables dampening.

CriticalLoadPropertyValue

```
typedef unsigned long CriticalLoadPropertyValue;
```

The critical-load load balancing strategy property value. The default value is 0, which disables re-balancing.

Constants**MEMBER_POLICY_ID**

```
const CORBA::PolicyType MEMBER_POLICY_ID = 1000;
```

This policy type identifies the member policy.

TolerancePropertyName

```
const string TolerancePropertyName = "tolerance";
```

The tolerance load balancing strategy property name. Members with a load difference that is less than tolerance are considered to have the same load.

LoadPerClientPropertyName

```
const string LoadPerClientPropertyName = "load-per-client";
```

The load-per-client load balancing strategy property name. The load-per-client property is an estimate of the load produced by a client.

RejectLoadPropertyName

```
const string RejectLoadPropertyName = "reject-load";
```

The reject-load load balancing strategy property name. Only members with loads less than reject-load are selected.

DampeningMultiplierPropertyName

```
const string DampeningMultiplierPropertyName =
    "dampening-multiplier";
```

The dampening-multiplier load balancing strategy property name. A dampening technique is used to smooth out spikes that may occur in the reported loads of members. The load of a member is calculated using the dampening-multiplier property as follows:

$$\text{load} = \text{mult} * \text{old_load} + (1 - \text{mult}) * \text{new_load}$$

where `mult` is the dampening-multiplier property value. The dampening-multiplier property must be greater than or equal to 0 and less than 1.

CriticalLoadPropertyName

```
const string CriticalLoadPropertyName = "critical-load";
```

The critical-load load balancing strategy property name. Members with loads greater than or equal to the critical-load are re-balanced.

Enums

PropertyErrorCode

```
enum PropertyErrorCode
{
    BAD_PROPERTY,
    BAD_VALUE
};
```

This enumeration contains the various load balancing strategy configuration property error codes.

Structs

Property

```
struct Property
{
    PropertyName name;
    PropertyValue value;
};
```

A load balancing strategy configuration property.

PropertyError

```
struct PropertyError
{
    PropertyName name;
    PropertyErrorCode code;
};
```

A load balancing strategy configuration property error.

MemberData

```
struct MemberData
{
    MemberId member_id;
    LoadAlert alert;
};
```

The member data.

MemberPolicyValue

```
struct MemberPolicyValue
{
    GroupId group_id;
    MemberId member_id;
};
```

The member policy value.

Exceptions

MemberExists

```
exception MemberExists
{
};
```

A MemberExists exception indicates that a member with the specified id is already exists in the load balanced group.

MemberNotFound

```
exception MemberNotFound
{
};
```

A MemberNotFound exception indicates that the specified member does not exist in the load balanced group.

GroupExists

```
exception GroupExists
{
```

```
};
```

A GroupExists exception indicates that a load balanced group with the specified id already exists.

GroupNotFound

```
exception GroupNotFound
{
};
```

A GroupNotFound exception indicates that the specified load balanced group does not exist.

StrategyNotFound

```
exception StrategyNotFound
{
};
```

A StrategyNotFound exception indicates that the specified strategy is not supported by the Balancer.

StrategyNotAdaptive

```
exception StrategyNotAdaptive
{
};
```

A StrategyNotAdaptive exception indicates that the strategy is not an adaptive strategy and does not require load updates.

InvalidProperties

```
exception InvalidProperties
{
    PropertyErrorSeq error;
};
```

An InvalidProperties exception indicates that specified properties were not valid and could not be used to create the strategy.

Interface LoadBalancing::LoadAlert

```
interface LoadAlert
```

Implemented by a server that wishes to receive load alerts (a signal to redirect requests back to the Balancer).

Operations

alert

```
void alert();
```

Redirect the next request back to the Balancer.

Interface LoadBalancing::Strategy

```
interface Strategy
```

Used to choose the next member to service a new client connection. The Balancer provides several implementations of the Strategy interface.

Operations

get_name

```
string get_name();
```

Retrieve the name of the strategy.

get_properties

```
PropertySeq get_properties();
```

Get the property set of the strategy.

adjust

```
void adjust(in MemberDataSeq members);
```

Update the members.

get_next

```
MemberId get_next()  
    raises (MemberNotFound);
```

Get an un-loaded member.

push_load

```
void push_load(in MemberId member_id,  
              in unsigned long load)  
    raises (MemberNotFound,  
          StrategyNotAdaptive);
```

Update the load of a member.

destroy

```
void destroy();
```

Destroy the strategy.

Interface LoadBalancing::StrategyProxy

```
interface StrategyProxy
```

Acts as a proxy for the load balancing strategy.

Operations

get_name

```
string get_name();
```

Retrieve the name of the strategy.

get_properties

```
PropertySeq get_properties();
```

Get the property set of the strategy.

push_load

```
void push_load(in MemberId member_id,  
              in unsigned long load)  
    raises (MemberNotFound,  
           StrategyNotAdaptive);
```

Update the load of a member.

Interface LoadBalancing::Group

```
interface Group
Represents a load balanced group.
```

Operations

get_id

```
GroupId get_id();
Get the id of the load balanced group.
```

get_ior

```
Object get_ior(in string repository_id,
               in ObjectId oid);
Get an IOR for use by a client of this load balanced group.
```

get_strategy_proxy

```
StrategyProxy get_strategy_proxy();
Get the strategy proxy of the load balanced group.
```

set_strategy

```
void set_strategy(in string name,
                  in PropertySeq properties)
    raises (StrategyNotFound,
           InvalidProperties);
Use the specified built-in load balancing strategy.
```

set_custom_strategy

```
void set_custom_strategy(in Strategy the_strategy);
Use the given custom load balancing strategy.
```

add_member

```
void add_member(in MemberId member_id)
    raises (MemberExists);
Add a member to the load balanced group.
```

remove_member

```
void remove_member(in MemberId member_id)
    raises (MemberNotFound);
Remove a member of the load balanced group.
```

set_load_alert

```
void set_load_alert(in MemberId member_id,
```



```
        in LoadAlert alert)  
    raises (MemberNotFound);
```

Set the LoadAlert object for a member.

list_members

```
MemberIdSeq list_members();
```

Enumerate the members.

destroy

```
void destroy();
```

Destroy the load balanced group.

Interface LoadBalancing::GroupFactory

```
interface GroupFactory
```

Used to create, destroy and retrieve load balanced groups.

Operations

create

```
Group create(in GroupId group_id)  
    raises(GroupExists);
```

Create a new load balanced group with the given id.

get

```
Group get(in GroupId group_id)  
    raises(GroupNotFound);
```

Get the load balanced group with the given id.

list

```
GroupIdSeq list();
```

List the set of existing load balanced groups.

shutdown

```
void shutdown();
```

Shutdown the Balancer.

Module LoadBalancing::Util

The definitions in this module provide the interface for the Orbacus Balancer utility objects that are provided by the Balancer. These utility objects can be used to implement the features required by load balanced servers that use adaptive load balancing.

Interface LoadBalancing::Util::LoadAlert

```
local interface LoadAlert
```

Interface to manage load alerts sent by the Balancer.

Operations

alert

```
void alert();
```

Forward the next request to the Balancer.

get_alert_expire

```
unsigned long get_alert_expire();
```

Retrieve the alert expire time.

set_alert_expire

```
void set_alert_expire(in unsigned long millis);
```

Set the alert expire time.

Interface LoadBalancing::Util::LoadCalculator

```
local interface LoadCalculator
```

Interface for the calculation of the server load.

The LoadCalculator is used by the LoadUpdater to calculate the current load of the server (which will be used as the load of each member registered with the LoadUpdater). The implementation provided by the Balancer calculates the load based on the number of active requests since the last invocation of `calculate_load()`.

See Also:

[“Interface LoadBalancing::Util::LoadUpdater”](#)

Operations

calculate_load

```
unsigned long calculate_load();
```

Calculate the load.

Interface LoadBalancing::Util::LoadUpdater

```
local interface LoadUpdater
```

Interface to manage load updates sent to the Balancer.

At regular intervals (set by the update frequency) the LoadUpdater gets the load from the LoadCalculator and pushes it to the load balanced group of each registered member.

See Also:

[“Interface LoadBalancing::Util::LoadCalculator”](#)

Operations

get_update_frequency

```
unsigned long get_update_frequency();
```

Retrieve the load push frequency.

set_update_frequency

```
void set_update_frequency(in unsigned long millis);
```

Set the load push frequency.

set_load_calculator

```
void set_load_calculator(in LoadCalculator calc);
```

Set the load calculator.

register_member

```
void register_member(in MemberId member_id,
                    in GroupId group_id)
    raises(GroupNotFound);
```

Register a load balanced group member.

unregister_member

```
void unregister_member(in MemberId member_id,
                      in GroupId group_id);
```

Unregister a load balanced group member.

Orbacus

Bibliography

- [1] Buschman, F., et al. 1996. *Pattern-Oriented Software Architecture: A System of Patterns*. New York: Wiley.
- [2] Gamma, E., et al. 1994. *Design Patterns*. Reading, MA: Addison-Wesley
- [3] Henning, M., and S. Vinoski. 1999. *Advanced CORBA Programming with C++*. Reading, MA: Addison-Wesley.
- [4] Object Management Group. 1999. *The Common Object Request Broker: Architecture and Specification*. Revision 2.3.1. <ftp://www.omg.org/pub/docs/formal/99-10-07.pdf>. Framingham, MA: Object Management Group.
- [5] Object Management Group. 1999. *C++ Language Mapping*. <ftp://www.omg.org/pub/docs/formal/99-07-45.pdf>. Framingham, MA: Object Management Group.
- [6] Object Management Group. 1999. *IDL/Java Language Mapping*. <ftp://www.omg.org/pub/docs/formal/99-07-53.pdf>. Framingham, MA: Object Management Group.
- [7] Object Management Group. 1999. *Portable Interceptors*. <ftp://ftp.omg.org/pub/docs/orbos/99-12-02.pdf>. Framingham, MA: Object Management Group.
- [8] Object Management Group. 1998. *CORBA Messaging*. <ftp://ftp.omg.org/pub/docs/orbos/98-05-06.pdf>. Framingham, MA: Object Management Group.
- [9] Object Management Group. 1998. *CORBA Services: Common Object Services Specification*. <ftp://www.omg.org/pub/docs/formal/98-12-09.pdf>. Framingham, MA: Object Management Group.
- [10] Object Management Group. 1999. *Naming Service Specification*. <ftp://ftp.omg.org/pub/docs/ptc/99-12-03.pdf>. Framingham, MA: Object Management Group.

BIBLIOGRAPHY

- [11] Schmidt, D. C. 1995. "Reactor: An Object Behavioral Pattern for Concurrent Event Demultiplexing and Event Handler Dispatching." In *Pattern Languages of Program Design*, ed. James O. Coplien and Douglas C. Schmidt. Reading, MA: Addison-Wesley.

Index

A

amirouter 356

B

Basic Object Adapter 112

Bindings 219

BOA 112

C

Callbacks 107

Command-line Options 88

Concurrency Models

 Threaded 376

 Thread-per-Client 378

 Thread-per-Request 379

 Thread Pool 380

Configuration File 90

Currently Executing Request 144

D

Documenting IDL Files 65

E

Event Channel 268

Event Consumers 269

Event Loop 109

Event Service 259

Event Suppliers 269

Exceptions 425

H

Hello World example application 26

Hostname 153, 393

HTML 65

I

IFR 279

Implementation Repository 179, 181

Implementation Repository Administration 192

IMR 179, 181

IMR Console 203

included IDL files 64

Initial Services 166, 176

 Configuring 173

 Resolving 171

Interface Repository 279

IP Address 395, 397

irdel 286

irfeed 286

J

javadoc 68

N

Names Console 233

Name Service

 Configuration 215

 Initialization 223

 Persistence 216

O

OAD 181

Object Activation Daemon 181

Object Adapter

 Configuration 85

 Initialization 76

Object Key 155

Object References 148

Objects

 Locating 147

 Persistent 134

 Transient 134

OCI 387

 Acceptor 388

 Acceptor Factory 388

 Bi-directional Plug-in 413

 Connector 388

 Connector Factory 388

 IIO Plug-in 399, 404, 413

 Info Objects 389

 Registries 388

 Transport 388

ooc.router.decay_policy.decay_ seconds 358

- ooc.router.resume_policy.resume_seconds 358
- ooc.router.retry_policy 357
- ooc.router.retry_policy.backoff_factor 357
- ooc.router.retry_policy.base_interval 357
- ooc.router.retry_policy.interval_limit 358
- ooc.router.retry_policy.max_backoffs 357
- Open Communications Interface 387
- Options
 - hidl 59
 - irgen 62
 - jidl 57
 - ridl 60
- ORB
 - Configuration 78
 - Destruction 108
- ORBacus Names 209

- P**
- POA 112, 184
- POA Manager 97
 - Root POA Manager 98
- Policies 329
 - ACMTimeoutPolicy 331
 - BidirectionalPolicy 331
 - ConnectionReusePolicy 331
 - ConnectTimeoutPolicy 331
 - InterceptorCallPolicy 333
 - InterceptorPolicy 332
 - LocationTransparencyPolicy 332
 - ProtocolPolicy 332
 - RequestTimeoutPolicy 332
 - RetryPolicy 333
 - TimeoutPolicy 333
- Popup Menu 245
- Port 154, 393
- Portable Object Adapter 112
- Programming Examples
 - Event Service 275
 - Implementation Repository 198, 310
 - Interface Repository 287
 - Name Service 222
 - OCI 391
 - Policies 334
 - Property Service 256
- Properties
 - ooc.config 78
 - ooc.event.max_events 263
 - ooc.event.max_retries 263
 - ooc.event.port 263
 - ooc.event.pull_interval 263
 - ooc.event.retry_multiplier 263
 - ooc.event.retry_timeout 263
 - ooc.event.trace.events 264
 - ooc.event.trace.lifecycle 264
 - ooc.event.typed_service 264
 - ooc.ifr.options 283
 - ooc.ifr.port 283
 - ooc.imr.dmdir 190, 298, 309
 - ooc.imr.trace.oad 190, 298, 309
 - ooc.naming.callback_timeout 215
 - ooc.naming.database 215
 - ooc.naming.no_updates 215
 - ooc.naming.port 215
 - ooc.naming.timeout 215
 - ooc.naming.trace_level 215
 - ooc.oci.client 78
 - ooc.oci.plugin 78
 - ooc.oci.server 78
 - ooc.orb.client_timeout 79
 - ooc.orb.conc_model 79
 - ooc.orb.default_init_ref 79
 - ooc.orb.default_wcs 79
 - ooc.orb.extended_wchar 79
 - ooc.orb.giop.max_message_size 79
 - ooc.orb.id 80
 - ooc.orb.module.name 80
 - ooc.orb.modules 80
 - ooc.orb.native_cs 80
 - ooc.orb.native_wcs 80
 - ooc.orb.oa.conc_model 85
 - ooc.orb.oa.endpoint 86
 - ooc.orb.oa.numeric 87
 - ooc.orb.oa.thread_pool 86
 - ooc.orb.oa.version 86
 - ooc.orb.poamanager.manager.conc_model 87
 - ooc.orb.poamanager.manager.endpoint 87
 - ooc.orb.poamanager.manager.version 87
 - ooc.orb.policy.connection_reuse 81
 - ooc.orb.policy.connect_timeout 81
 - ooc.orb.policy.interceptor 81
 - ooc.orb.policy.locate_request 81
 - ooc.orb.policy.location_transparency 81
 - ooc.orb.policy.protocol 81
 - ooc.orb.policy.rebind 81
 - ooc.orb.policy.request_timeout 81
 - ooc.orb.policy.retry 82
 - ooc.orb.policy.retry.interval 82
 - ooc.orb.policy.retry.max 82

- ooc.orb.policy.retry.remote 82
- ooc.orb.policy.sync_scope 82
- ooc.orb.policy.timeout 82
- ooc.orb.server_name 82
- ooc.orb.server_shutdown_timeout 83
- ooc.orb.server_timeout 83
- ooc.orb.service.name 83
- ooc.orb.trace.connections 84
- ooc.orb.trace.retry 84
- ooc.orb.use_type_code_cache 83
- ooc.property.port 248
- Property Service 247

R

- Reactor 382
- Recursion 237
- RTF 65

S

- Servants 114
 - Activation 128
 - C++ 124

- Deactivation 133
- Delegation 118
- Inheritance 115
- Java 126

T

- Toolbar 206, 244

U

- URL 159, 160
 - corbaloc 161
 - corbaname 163
 - file 164
 - relfile 165

W

- Windows Reactor 385
- Windows Registry 91

X

- X11 Reactor 383

